

# Programmer's Reference Guide for 8810A

Two Synchro/Resolver Measurement and One optional Reference supply

# Programmer's Reference Guide for 8810A



# Table of Contents

1	Intro	oduction	3
2		note Setup	
	2.1	Controlling Channel 1 Signal Input	
3		guage Supportguage Support	
	3.1	Compatibility to 8810 APIs	
	3.1.	1 8810-FX2 Emulation Mode	
	3.2	Language Independent Commands	11
	3.3	API-8810A Native	
	3.4	API-8810 Native (Legacy)	32
	3.5	API-8810 SR103 (Legacy)	34
	3.7	API-8810 HSR202 (Legacy)	35
	3.8	API-8810 HSR203 (Legacy)	36
	3.9	API-8810 MATE/CIIL (Legacy)	
4	API	-8810A USB Protocol	38
5	API	-8810A Ethernet Protocol	40
6	API	-8810A DLL	43
7	API	-8810A Soft Panel Program	44
8	Cyp	oress USB Driver Installation	52

### 1 Introduction

The 8810A Angle Position Indicator Measurement Instrument provides two fully independent channels with 0.0001° resolution and 0.004° (Standard)/ 0.001° (Special) accuracy. The 8810A allows all programming to be done via the touch-screen or mouse interface. In addition, remote operation capabilities are provided via IEEE-488, USB, Ethernet and J1 connection (50 pin DSUB connector in back of the unit).

#### **Reference Documentation**


For additional information about this instrument refer to the *Operation Manual for Model 8810A*. For additional information about the Application Programming Interface (API) provided in the API8810ADll refer to the *Function Reference Manual for 8810A*.

#### **Reference CD**


For electronic copies of the 8810A documentation, API-8810A Soft Panel application program, and source code for API-8810ADll and Soft Panel application refer to the 8810A Product CD.

# 2 Remote Setup

To enable remote operation capabilities via IEEE-488, USB, Ethernet and J1 connection (50 pin DSUB connector in back of the unit), the unit must be configured for remote operation.



Click on the button labeled "Loc/Rem" to view the Local/Remote Configuration screen:




In "Local" mode, the configuration settings can be queried. The unit must be in one of the "Remote" modes (Ethernet, IEEE, USB or J1) before configuration settings can be changed remotely. Note, for remote programming via the IEEE interface, the language type must be selected, refer to section 3 on language support.

### 2.1 Controlling Channel 1 Signal Input

The signal input for channel 1 can be read from the front panel connector or from the J1 connection in the back of the unit. The signal input for channel 2 is read only from the J1 connection.


The configuration for channel 1 is configured two ways:

One method is to click the button shown below:






Button configures Chan 1 Input to be read from the Front Connector or the Back (J1) Connector.



Click the "Options" button.



Select the "Front Panel" or "Back Connector" option for Channel 1 Input. Click on the "Set" button.



Note: the "Auto Save" option is not available on 8810A Revision B instruments.

# **Language Support**

The 8810A Unit is a direct replacement for all 8810's. This unit supports the following languages:

	IEEE-488.1	USB	Ethernet
API-8810A Native	Supported	Supported	Supported
API-8810 Native (Legacy)	Supported	Not available	Not available
<b>API-8810 SR103 (Legacy)</b>	Supported	Not available	Not available
API-8810 HSR202	Supported	Not available	Not available
(Legacy)			
API-8810 HSR203	Supported	Not available	Not available
(Legacy)			
API-8810 MATE/CIIL	Please contact	Not available	Not available
(Legacy)	manufacturer for		
	MATE/CIIL		
	support		
API-8810-FX2 (Legacy)	Supported	Not available	Not available

The following table lists the applicable IEEE-488 bus commands for the API-8810A.

Mnemonic	ASCII	Hex	Function	
GTL	SOH	01	Go To Local - This command instructs the API to go to local	
			mode. All front panel controls are active.	
SDC	EOT	04	Selected Device Clear - When the SDC command is	
			received, and if the API is addressed to listen, the API will	
DO!	504	4.4	initialize to the conditions listed under DCL.	
DCL	DC4	14	Device Clear - When the API receives the DCL command it	
			is initialized to the following state:	
			0.4101100	
			SYNCHRO	
			DATA FREEZE - OFF	
			SRQ MODE - OFF	
OFT	DC	00	GET MODE – OFF	
GET	BS	08	Group Execute Trigger - When the GET command is	
			received, and if the API is addressed to listen and has the	
			GET mode switch on, data sent to the API will be applied to the instrument.	
LLO	DC1	11	Local Lockout - This command disables the front panel	
	201		REM switch. It gives the controller complete control over	
			whether the API is in remote or local operation.	
SPE	CAN	18	Serial Poll Enable - After receipt of this command the API,	
			when addressed to talk, will transmit the Status Byte.	
SPD	EM	19	Serial Poll Disable - This command cancels the SPE	
			command and allows the API, when it is addressed to talk,	
			to send data.	
UNL	/	3F	Unlisten - Unaddresses the API listen address.	
UNT	-	5F	Untalk - Unaddresses the API talk address.	

The following table lists the interface function capability codes for the API-8810A.

Code	Function
AH1	Acceptor handshake - complete capability
SH1	Source handshake - complete capability
T6	Talk capability - all except TON
TEO	Extended Talk capability – none
L4	Listen capability - all except LON
LEO	Extended Listen capability - none
SR1	Service request - complete capability
RL1	Remote/Local - complete capability
PPO	Parallel Poll - no capability
DC1	Device Clear - complete capability
DT1	Device Trigger - complete capability

### 3.1 Compatibility to 8810 APIs

The 8810A will provide language compatibility to the following 8810 systems:

- API-8810 Native
- API-8810 SR103
- API-8810 HSR202
- API-8810 HSR203

#### **Legacy 8810 Native Data**

When the IEEE language type selected is 8810 Native legacy languages, the API will send angle data to the controller in the following format:

The standard API data message will always be 7 characters long plus a <cr><lf>. The API when used in the ±180 mode will send angle data to the IEEE controller in the following format:

The ±180 degree data message will always be eight characters long plus a <CR><LF>.

#### Legacy 8810 SR103, HSR202 and HSR203 Data

When the IEEE language type selected is one of the 8810 legacy languages (SR103, HSR202 or HSR203), the API will send angle data to the controller in the following format:

The standard API data message will always be 7 characters long plus a <cr><lf>. The API when used in the ±180 mode will send angle data to the IEEE controller in the following format:

The ±180 degree data message will always be seven characters long plus a <CR><LF>.

#### **Serial Poll**

When the IEEE language type selected is one of the 8810 legacy languages, the status byte returned by the API indicates the status of the instrument. The bits of the status byte are defined as:

D7	D6	D5	D4	D3	D2	D1	D0
ERROR	RQS	0	0	0	0	FREEZE	RESOLVER

**ERROR** -When bit is set the API data is not stable. If FREEZE is programmed, this bit will always be 0.

**RQS** -When bit is set the API is asserting the SRQ line.

**FREEZE** -When bit is set the display is frozen.

**RESOLVER** -When bit is set the API is programmed for RESOLVER mode. When cleared the API is set to SYNCHRO mode.

If the RQS bit is set, the remaining bits indicate the state of the API when the SRQ line was last asserted. If the RQS line is not set then the remaining bits indicate the state of the API at the time the status byte is read.

**Service Request** The API can be programmed to assert the SRQ line when the display data is stable. Stability is defined as the angle readings being within <TBD> degrees or the FREEZE mode is programmed. The V command instructs the API to assert the SRQ line when stable data is detected. If stability is not detected within 4 seconds, SRQ will be asserted nevertheless and the ERROR bit in the STATUS byte will be set. This command cancels itself once SRQ is asserted and must be reprogrammed for subsequent SRQs. When SRQ is asserted the display data is saved and will be transmitted to the controller (when addressed to talk) regardless of the display value. Once read, the API output data will then agree with the display.

**GET Mode** When the G command is included in the programming string, the API will hold off applying the programming data until the GET (Group Executive Trigger) bus command is received. GET mode is cancelled once the bus command GET is received and must be reprogrammed if desired again.

#### 3.1.1 8810-FX2 Emulation Mode

In addition to providing language compatibility to legacy 8810 units, the 8810A provides an emulation mode for the 8810-FX2. Under the 8810-FX2 language type, the following settings are automatically configured:

- 1. The Channel 1 Connector is set to BACK connector.
- 2. The Reference Sources for Channel 1 and Channel 2 are set to EXT.
- 3. Channel 1 is set to SYN mode and Channel 2 is set to RSL mode.
- 4. The Angle Display Format is set to 0->359.9999 (Note, the resolution selection will not be altered this give the user the flexibility to choose how many digits to display)
- 5. Ratio is set to 1.
- 6. When in 8810-FX2, at power-on of the unit the above settings will be the default.

# 3.2 Language Independent Commands

Note the following commands are case-sensitive.

Function	Syntax (commands must be sent with upper-case)	Comments				
	API COMMANDS					
Identification	*IDN? <cr><lf></lf></cr>	Queries the device				
		for the ID.				
Error	*ERR? <cr><lf></lf></cr>	Queries for any				
Reporting		error messages on				
		the error message				
		queue. "No error"				
		is returned when				
		there are no errors				
		on the queue.				
Reset	*RST? <cr><lf></lf></cr>	Clears the error				
		message queue and				
		resets the device				
		with default factory				
		settings." Reset				
		Complete" is				
		returned when				
		device is reset to				
		the default settings.				
		"Reset Not				
		Performed" is				
		returned if the				
		device's remote				
		configuration does				
		not match				
		communication				
		connection mode.				

Language	APICMD <b>LANG?<cr><lf></lf></cr></b>	Queries the IEEE
		Language setting.
		Query returns:
		'API8810A
		Native', or
		'API8810 Native',
		or 'API8810
		SR103', or
		'API8810
		HSR202', or
		'API8810
		HSR203', or
		"API8810
		MATE/CIIL' or
		"API8810 FX2"
	APICMD <b>LANG<b>&lt; 8810ANATIVE 8810NATIVE </b></b>	Sets the IEEE
	8810SR103 8810HSR202 8810HSR203 8810MATECIIL	Language setting.
	8810FX2> <cr><lf></lf></cr>	

### 3.3 API-8810A Native

The API-8810A Native language is support via the IEEE-488.1, USB and Ethernet interfaces. The language provides remote programming access to the features available on the 8810A unit. Note the following commands are case-sensitive.

	API CHANNELS				
Function	Syntax (commands must be sent with upper-case)	Comments			
Track/Latch	API <chan><b>UPDATE?<cr><lf></lf></cr></b></chan>	Queries the			
Angle		track/latch state of			
		the channel.			
		Query returns:			
		'LATCHED' or			
		'TRACK'.			
	API <chan><b>UPDATE<b><latch track><cr><lf></lf></cr></latch track></b></b></chan>	Sets the track/latch			
		state for the channel.			
Signal	API <chan><b>MODE?<cr><lf></lf></cr></b></chan>	Queries the mode			
Mode		state of the channel.			
		Query returns: 'RSL'			
		or SYN'.			
	API <chan><b>MODE<b><rsl syn><cr><lf></lf></cr></rsl syn></b></b></chan>	Sets the Rsl/Syn state			
		for the channel.			
Reference	API <chan><b>REF_SOURCE?<cr><lf></lf></cr></b></chan>	Queries the reference			
Mode		source for the			
		channel.			
		Query returns: 'INT'			
		or 'EXT'.			
	API <chan><b>REF_SOURCE<b><int ext><cr><lf></lf></cr></int ext></b></b></chan>	Sets the			
		Internal/External			
		reference source			
		mode for the channel.			
Ratio	API <chan><b>RATIO?<cr><lf></lf></cr></b></chan>	Queries the ratio			
		setting for each			
		channel.			
		Query returns the '1'			
		always for channel 1			
		and for channel 2, the			
		ratio setting value:			
		Ratio Range = 1 to			
		255.			

	API <chan><b>RATIO<b><value><cr><lf></lf></cr></value></b></b></chan>	Sets the ratio setting for each channel. Channel 1 can only be set to 1. Channel 2 can be set to any value between 1 and 255.
Bandwidth	API <chan><b>BANDWIDTH?<cr><lf></lf></cr></b></chan>	Queries the bandwidth setting for each channel. Query returns: AUTO bwValue or OVERRIDE
		bwValue
	API <chan><b>BANDWIDTH<b><auto><cr><lf></lf></cr></auto></b></b></chan>	Sets the channel to auto-bandwidth mode.
	API <chan><b>BANDWIDTH<b><set><value><cr><lf< td=""><td>Sets the channel</td></lf<></cr></value></set></b></b></chan>	Sets the channel
	>	bandwidth value Range: 6 <= value <= 1200
Angle Averaging	API <chan><b>AVERAGE?<cr><lf></lf></cr></b></chan>	Queries the averaging setting for the channel. Query returns:  ON avgRate or  OFF avgRate
	API <chan><b>AVERAGE<b>STATE<b><on off> <cr><lf></lf></cr></on off></b></b></b></chan>	Turns on or off the channel's averaging feature.
	API <chan><b>AVERAGE<b>RATE?<cr><lf></lf></cr></b></b></chan>	Queries the averaging setting for the averaging rate in msec for the channel.
	API <chan><b>AVERAGE<b>RATE<b><value><cr><lf></lf></cr></value></b></b></b></chan>	Set the channel's averaging rate in msec. Range: 10<= value <= 10000.

	API <chan><b>AVG_ANGLE?<cr><lf></lf></cr></b></chan>	Queries the average angle value for the channel. Query returns angle in degrees: Range: 0.0000 < value < 359.9999 or Bipolar Range: -180.0000 < value < +180.0000
Angle Limit Testing	API <chan><b>ANG_LIMIT?<cr><lf></lf></cr></b></chan>	Queries the angle limit test settings for the channel. Query returns: 'ON' or 'OFF' to indicate whether limit testing is active or disable, a blank space, 'ABS' or 'ERR' to indicate whether absolute angle or angle error comparison is used for limit testing.
	API cohons do ANC LIMIT do CMP2 cons de	Turns on or off the channel's angle limit testing feature.
	API <chan><b>ANG_LIMIT<b>CMP?<cr><lf></lf></cr></b></b></chan>	Queries the angle limit test comparison settings for the channel.  Query returns 'ABS' or 'ERR'.
	API <chan><b>ANG_LIMIT<b>CMP<b><abs err> <cr><lf></lf></cr></abs err></b></b></b></chan>	Set the channel's angle limit comparison to Absolute Angle or Angle Error.

API <chan><b>ANG_LIMIT<b>HI?<cr><lf></lf></cr></b></b></chan>	Queries the upper limit test value settings for the channel. Query returns upper limit in degrees: Range: 0.0000 < value < 359.9999 or Bipolar Range: -180.0000 < value < +180.0000
API <chan><b>ANG_LIMIT<b>HI<b><value><cr><lf></lf></cr></value></b></b></b></chan>	Sets the upper limit test value in degrees: Range: 0.0000 < value < 359.9999 or Bipolar Range: -180.0000 < value < +180.0000
API <chan><b>ANG_LIMIT LO?<cr><lf></lf></cr></b></chan>	Queries the lower limit test value settings for the channel. Query returns lower limit in degrees: Range: 0.0000 < value < 359.9999 or Bipolar Range: -180.0000 < value < +180.0000
API <chan><b>ANG_LIMIT<b>LO<b><value><cr><lf></lf></cr></value></b></b></b></chan>	Sets the lower limit test value in degrees: Range: 0.0000 < value < 359.9999 or Bipolar Range: -180.0000 < value < +180.0000

	API <chan><b>ANG_LIMIT STEP?<cr><lf>API<chan><b>ANG_LIMIT<b>STEP<b><value><cr><lf><cr><lf></lf></cr></lf></cr></value></b></b></b></chan></lf></cr></b></chan>	Queries the angle step value for limit test value settings for the channel. Query returns step value in degrees: Range: 0.001 < value < 359.999  Sets the angle step test value in degrees: Range: 0.0000 < value < 359.9999 or Bipolar Range: -180.0000 < value <
Angle	API <chan><b>ANGLE?<cr><lf></lf></cr></b></chan>	+180.0000  Queries the angle data for the channel.  Query returns angle in degrees:  Range: 0.0000 < value < 359.9999  or  Bipolar Range: -180.0000 < value < +180.0000
Velocity	API <chan><b>VEL?<cr><lf></lf></cr></b></chan>	Queries the angle velocity data for the channel. Query returns channel velocity in degrees per second: Range: -32767 < value < +32767.
Line-to- Line Voltage	API <chan><b>LL_VOLT?<cr><lf></lf></cr></b></chan>	Queries the line-to- line voltage for the channel.
Null Voltage	API <chan><b>NULL_VOLT?<cr><lf> API<chan><b>REF_VOLT?<cr><lf></lf></cr></b></chan></lf></cr></b></chan>	Queries the null voltage for the channel. Note this feature has not been implemented. The value 0.00 will always be returned. Queries the reference

Voltage		voltage for the channel.
Reference	API <chan><b>REF_FREQ?<cr><lf></lf></cr></b></chan>	Queries the reference
Frequency	THE TOTAL TREE, SET SHOW	frequency for the
requestey		channel.
Digital-to-	API <chan><b>DA<b>OUTPUT?<cr><lf></lf></cr></b></b></chan>	Queries the D/A
Analog		setup for the data to
Setup		use for D/A voltage
lr		output conversion for
		the channel.
		Query returns 'ANG'
		or 'VEL'.
	API <chan><b>DA<b>OUTPUT<b><ang vel></ang vel></b></b></b></chan>	Sets the D/A data to
	<cr><lf></lf></cr>	use either angle or
		velocity for D/A
		voltage output
		conversion for the
		channel.
	API <chan><b>DA<b>HIDATA?<cr><lf></lf></cr></b></b></chan>	Queries the D/A
		Upper Limit Data
		conversion for the
		channel.
		Query returns for
		Angle Data in
		degrees:
		Unipolar Range:
		0.0000 < value <
		359.9999
		or Bipolar Range:
		-180.0000 < value <
		+180.0000
		Query returns for
		Velocity Data in
		degrees/sec:
		Range:
		-10000 <value<10000< td=""></value<10000<>

API <chan><b>DA<b>HIDATA<b><value><cr><lf></lf></cr></value></b></b></b></chan>	Sets the D/A Upper Limit Data conversion for the channel. Angle Data Range in degrees: Unipolar Range:
	conversion for the channel. Angle Data Range in degrees: Unipolar Range:
	channel. Angle Data Range in degrees: Unipolar Range:
	Angle Data Range in degrees: Unipolar Range:
	degrees: Unipolar Range:
	Unipolar Range:
	1
	0.0000 < value <
	359.9999
	or Bipolar Range:
	-180.0000 < value <
	+180.0000
	Velocity Data Range
	in degrees/sec:
	-10000 <value<10000< td=""></value<10000<>
API <chan><b>DA<b>HIVOLT?<cr><lf></lf></cr></b></b></chan>	Queries the D/A
	Voltage conversion
	for the Upper Limit
	Conversion for the
	channel.
	Query returns voltage
	value in the range:
	-10.0 <value<10.0< td=""></value<10.0<>
API <chan><b>DA<b>HIVOLT<b><value><cr><lf></lf></cr></value></b></b></b></chan>	Sets the D/A Voltage
	conversion for the
	Upper Limit
	channel.
	C C
	-10.0 <value<10.0< td=""></value<10.0<>
	Voltage range in volts:

ADI cohomo do DA do LODATAO con 10	Oversion the D/A
API <chan><b>DA<b>LODATA?<cr><lf></lf></cr></b></b></chan>	Queries the D/A
	Lower Limit Data
	conversion for the
	channel.
	Query returns for
	Angle Data in
	degrees:
	Unipolar Range:
	0.0000 < value <
	359.9999
	or Bipolar Range:
	-180.0000 < value <
	+180.0000
	Query returns for
	Velocity Data in
	degrees/sec:
	Range:
	-10000 <value<10000< td=""></value<10000<>
ADI cabana da DA da LODATA da cualva com de	
API <chan><b>DA<b>LODATA<b><value><cr><lf></lf></cr></value></b></b></b></chan>	Sets the D/A Lower
	Limit Data
	conversion for the
	channel.
	Angle Data Range in
	degrees:
	Unipolar Range:
	0.0000 < value <
	359.9999
	or Bipolar Range:
	-180.0000 < value <
	+180.0000
	Velocity Data Range
	in degrees/sec:
	-10000 <value<10000< td=""></value<10000<>
API <chan><b>DA<b>LOVOLT?<cr><lf></lf></cr></b></b></chan>	Queries the D/A
	Voltage conversion
	for the Lower Limit
	Conversion for the
	channel.
	Query returns voltage
	value in the range:
	-10.0 <value<10.0< td=""></value<10.0<>
	-10.0\varue\10.0

API <chan><b>DA<b>LOVOLT<b><value><cr><lf></lf></cr></value></b></b></b></chan>	Sets the D/A Voltage
	conversion for the
	Lower Limit
	Conversion for the
	channel.
	Voltage range in
	volts:
	-10.0 <value<10.0< td=""></value<10.0<>

# MULTIPLE CHANNEL QUERIES

Note: Channel 1 and Channel 2 data are returned with Channel 1 data first and then Channel 2 data, separated by a comma

Channel 2 data, separated by a comma		
Function	Syntax (commands must be sent with upper-case)	Comments
Angle	APIALL <b>ANGLE?<cr><lf></lf></cr></b>	Queries the angle data for BOTH channels. Query
		returns angle in
		degrees:
		Range: 0.0000 < value < 359.9999
		or Bipolar Range:
		-180.0000 < value <
		+180.0000
Angle Averaging	APIALL <b>AVERAGE?<cr><lf></lf></cr></b>	Queries the averaging setting for BOTH channels. Query
		returns:
		ON avgRate
		or OFF avgRate
	APIALL <b>AVG_ANGLE?<cr><lf></lf></cr></b>	Queries the average
		angle value for
		BOTH channels.
		Query returns angle
		in degrees:
		Range: 0.0000 < value < 359.9999
		or
		Bipolar Range: -180.0000 < value <
		+180.0000 < value < +180.0000
Bandwidth	APIALL <b>BANDWIDTH?<cr><lf></lf></cr></b>	Queries the
		bandwidth setting for
		BOTH channels.
		Query returns: AUTO bwValue
		or
		OVERRIDE
		bwValue
Signal	APIALL <b>MODE?<cr><lf></lf></cr></b>	Queries the mode
Mode		state of BOTH
		channels. Query returns: 'RSL' or

		SYN'.
Ratio	APIALL <b>RATIO?<cr><lf></lf></cr></b>	Queries the ratio
		setting for BOTH
		channels. Query
		returns '1' for
		channel 1 and for
		channel 2, the ratio
		setting: Ratio Range
		= 1  to  255.
Reference	APIALL <b>REF_SOURCE?<cr><lf></lf></cr></b>	Queries the reference
Mode		source for BOTH
		channels. Query
		returns: 'INT' or
		'EXT'.
Track/Latch	APIALL <b>UPDATE?<cr><lf></lf></cr></b>	Queries the
Angle		track/latch state of
		BOTH channels.
		Query returns:
		'LATCHED' or
		'TRACK'.
Angle Limit	APIALL <b>ANG_LIMIT?<cr>&lt;1f&gt;</cr></b>	Queries the angle
Testing		limit test settings for
		BOTH channels.
		Query returns:
		'ON' or 'OFF' to
		indicate whether limit
		testing is active or
		disable, a blank
		space,
		'ABS' or 'ERR' to
		indicate whether
		absolute angle or
		angle error
		comparison is used
		for limit testing.
Velocity	APIALL <b>VEL?<cr><lf></lf></cr></b>	Queries the angle
		velocity data for
		BOTH channels.
		Query returns
		channel velocity in
		degrees per second:
		Range: -32767 <
		value < +32767.
Line-to-	APIALL <b>LL_VOLT?<cr><lf></lf></cr></b>	Queries the line-to-
Line		line voltage for
Voltage		BOTH channels.

Null	APIALL <b>NULL_VOLT?<cr><lf></lf></cr></b>	Queries the null
Voltage	_	voltage for BOTH
		channels.
		Note this feature has
		not been
		implemented. The
		value 0.00 will
		always be returned.
Reference	APIALL <b>REF_VOLT?<cr><lf></lf></cr></b>	Queries the reference
Voltage		voltage for BOTH
_		channels.
Reference	APIALL <b>REF_FREQ?<cr><lf></lf></cr></b>	Queries the reference
Frequency		frequency for BOTH
		channels.

INTERNAL REFERENCE GENERATOR		
Function	Syntax (commands must be sent with upper-case)	Comments
Reference Generator Frequency	REF_GEN <b>FREQ?<cr><lf></lf></cr></b>	Queries the frequency setting for the internal reference generator.
	REF_GEN <b>FREQ<b><value><cr><lf></lf></cr></value></b></b>	Sets the frequency setting for the internal reference generator. Frequency range is 47.0 to 20000.0 Hz.
Reference Generator Voltage	REF_GEN <b>VOLT?<cr><lf></lf></cr></b>	Queries the voltage setting for the internal reference generator.
	REF_GEN <b>VOLT<b><value><cr><lf></lf></cr></value></b></b>	Sets the voltage setting for the internal reference generator. Voltage range is 2.0 to 115.0 volts.
Reference Generator Output State	REF_GEN <b>STATE?<cr><lf></lf></cr></b>	Queries the output state of the internal reference generator. Query returns: 'OPEN', or 'CLOSED'.
	REF_GEN <b>STATE<b>OPEN CLOSE&gt;<cr><lf></lf></cr></b></b>	Sets the output state for the internal reference generator. The CLOSE state will out allow reference signals to be available at the output connectors. The OPEN state will prevent the reference signals from being outputted.

Reference	REF_GEN <b>OV_CUR?<cr><lf></lf></cr></b>	Queries the internal
Generator		reference generator
Overcurrent		over-current state.
State		Query returns: 'NO
		OVER_CURR" or
		"OVER_CURR"
	REF_GEN <b>OV_CUR</b>	Resets the internal
		reference module's
		over-current state.

	API CONFIGURATION	
Function	Syntax (commands must be sent with upper-case)	Comments
Communication Setting	APICMD APICMD   APICMD   APICMD	Queries the communication settings. Possible results are: Local Mode or Remote IEEE Addr: API-IEEE Language or Remote USB or Remote Ethernet or Remote With Lockout via IEEE Addr: API-IEEE Language or Remote with Lockout via USB or Remote with Lockout via Ethernet or Remote with Lockout via Ethernet or Remote with Lockout via Ethernet or
	APICMD <b>COMM<b><ieee usb ethernet j1> <cr><lf></lf></cr></ieee usb ethernet j1></b></b>	Sets the communication setting to communicate remotely via IEEE, USB, Ethernet or J1.
Go To	APICMD <b>COMM<b><local><cr><lf></lf></cr></local></b></b>	Sets the device to
Local	LINGUID L. GOLDE L. YOUNG	Local mode.
Local Lockout	APICMD <b>COMM<b><lockout><cr><lf></lf></cr></lockout></b></b>	Sets the device to Local Lockout mode.
Angle Display Format	APICMD <b>ANG_FMT?<cr><lf></lf></cr></b>	Queries the angle display format.  Query returns:  ('0 to 360', or  '-180 to 180', or  'Deg, Min, Sec')

	APICMD <b>ANG_FMT<b>&lt;360 180 MIN&gt;<cr><lf></lf></cr></b></b>	Sets the angle display format.
Device Screen Display	APICMD <b>DISPLAY?<cr><lf></lf></cr></b>	Queries the display screen: Query returns: '0-DIG1', '1- DIG2','2-ANG1','3- ANG2','4-DUAL', '5-REF', or '6-CHART'
	APICMD <b>DISPLAY<b>&lt;0 1 2 3 4 5 6&gt;<cr>&lt;1f&gt;</cr></b></b>	Sets the display screen as follows: 0 – Digital Chan 1 1 – Digital Chan 2 2 – Analog Chan 1 3 – Analog Chan 2 4 – Dual Channels 5 – Reference 6 - Charting
Channel 1 Input Connector	APICMD <b>CH1INPUT?<cr><lf></lf></cr></b>	Queries the channel 1 input connector setting. Query returns: 'FRONT', or 'BACK'.
	APICMD <b>CH1INPUT<b><front back><cr><lf></lf></cr></front back></b></b>	Sets the channel 1 input connector setting to either the Front or Back connectors.
Angle Difference	APICMD <b>SHOWDIFF?<cr><lf></lf></cr></b>	Queries the device to determine if angle difference mode is ON or OFF.
	APICMD <b>SHOWDIFF<b><on off><cr><lf></lf></cr></on off></b></b>	Sets the device to show angle difference or Channel 2 angle value. If angle difference is turned ON, the device will automatically switch the screen to Dual Chan and show the angle difference value in place of Channel 2 angle data.

	APICMD <b>ANGDIFF?<cr><lf></lf></cr></b>	Queries the device for the angle difference between Channel 1 angle and Channel 2 angle value. Angle Diff Range: -180.0000 < value < +180.0000
Default Values	APICMD b>RSTFRAM <cr><lf></lf></cr>	Clears the error message queue and resets the device with default factory settings. Note, this command will also reset the calibration values and a calibration of the device is recommended after issuing this command.

No	API CHARTING AND BUFFERING te: Retrieval of the buffered data is available only via USB	or Ethernet!
Function	Syntax (commands must be sent with upper-case)	Comments
Charting	APIBUF <b>CNT? <cr><lf></lf></cr></b>	Queries the device
and Buffering		for the number of
		records in the buffer.
	APIBUF <b>RECORD? <cr><lf></lf></cr></b>	Queries the device
		for the recording
		state. Query returns:
		'NOT RECORDING'
		or 'RECORDING'
	APIBUF <b>RECORD<b><start stop clear></start stop clear></b></b>	Set the device to start
	<cr><lf></lf></cr>	or stop recording or
		to clear the buffer.
		The device will
		automatically switch
		the screen to Charting
		screen when this
		command is sent.
	APIBUF <b>SAMPLE_RATE?<cr><lf></lf></cr></b>	Queries the device
		for the sample rate
		for recording data.
		Query returns the
		sample interval,
		followed by a blank,
		and the sample units
		('MSEC', 'SEC' or
	ADIDLIE do CAMDLE DATE do grales do MCECICE	'MIN').
	APIBUF b>SAMPLE_RATE value> WSEC SE	Sets the device to
	C MIN> <cr><lf></lf></cr>	sample at the given
		rate. Sample Rate
		range: 100 msec < value <
		30 min
	APIBUF <b>SAMPLE TYPE?<cr><lf></lf></cr></b>	Queries the device
	AI IDUI (0/SAMI LE_I II E:\CI>\II)	for the type of data to
		record. Query
		returns: 'ANG',
		'ANGERR' or
		'VEL'.
	APIBUF <b>SAMPLE_TYPE<b><ang angerr vel></ang angerr vel></b></b>	Sets the device to
	<pre><r><li><cr><lf></lf></cr></li></r></pre>	record Angle, Angle
		Error or Velocity
		•
		data.

	APIBUF <b>PLOT_CH?<cr><lf></lf></cr></b>	Queries the device
		for the channel to
		plot. Query returns:
		'BOTH', 'CH1' or
		'CH2'
	APIBUF <b>PLOT_CH<b>BOTH CH1 CH2&gt;<cr><lf></lf></cr></b></b>	Sets the device to
	AFIBOT COSELOT_CITCOSCBOTTICITICITZS CISCITS	record BOTH
		channels, Channel 1
		only, or Channel 2
		only.
	APIBUF <b>CHAN<chan><b><recstart#><b><recstop#></recstop#></b></recstart#></b></chan></b>	Note, retrieval of the
	<cr><lf></lf></cr>	buffered data is
		available only via
		USB or Ethernet.
		Via USB, the
		maximum number of
		records returned for
		each call is 5.
		Via Ethernet, the
		maximum number of
		records returned for
		each call is 150.
Calibration	APICMD <b>CALIBRATE?<cr><lf></lf></cr></b>	Queries the device
		for the calibration
		state. Query returns:
		'CAL DONE' or
		'CALIBRATING'
	APICMD <b>CALIBRATE<cr><lf></lf></cr></b>	Calibrates the unit.
Periodic	APICMD <b>PERIODIC_CAL?<cr><lf></lf></cr></b>	Queries the device to
Calibration		determine if the
		periodic calibration is
		ON or OFF.
	APICMD <b> PERIODIC_CAL <b><on off><cr><lf></lf></cr></on off></b></b>	Enables or disables
		the periodic
		calibration.
	1	vanoration.

# 3.4 API-8810 Native (Legacy)

The API-8810 Native language is only support via the IEEE-488.1. The language is available to provide backwards compatibility to the 8810 units. Only the features that were available for the 8810 are supported with this language.

Function	Syntax	Comments
Track/Latch (Hold)	Serial Poll Status Byte	Queries the track/latch state of the
Angle		channel.
	F <cr><lf>or</lf></cr>	Set the latch state for the active channel.
	f <cr><lf>or</lf></cr>	
	>F <cr><lf> or</lf></cr>	
	>f <cr><lf></lf></cr>	
	T <cr><lf> or</lf></cr>	Set the track state for the active channel.
	t <cr><lf>or</lf></cr>	
	>T <cr><lf>or</lf></cr>	
	>t <cr><lf></lf></cr>	
Channel Select	S <cr><lf>or</lf></cr>	If Channel 1 Input is set for "Front
	s <cr><lf> or</lf></cr>	Panel", this will set the Signal Mode to
	>S <cr><lf> or</lf></cr>	SYNCHRO. Channel 1 is set as the
	>s <cr><lf> or</lf></cr>	active channel.
	1 <cr><lf>or</lf></cr>	If Channel Input is set for "Back
	>1 <cr><lf></lf></cr>	Connector" the Signal Mode
		configuration is not modified. Channel 1
		is set as the active channel.
	R <cr><lf> or</lf></cr>	If Channel 1 Input is set for "Front
	r <cr><lf> or</lf></cr>	Panel", this will set the Signal Mode to
	>R <cr><lf> or</lf></cr>	RESOLVER. Channel 1 is set as the
	>r <cr><lf> or</lf></cr>	active channel.
	2 <cr><lf>or</lf></cr>	If Channel Input is set for "Back
	>2 <cr><lf></lf></cr>	Connector" the Signal Mode
		configuration is not modified.
		Channel 2 is set as the active channel.
Angle Display Format	B <cr><lf> or</lf></cr>	Set the angle format to +/-180 degrees.
	b <cr><lf>or</lf></cr>	
	>B <cr><lf> or</lf></cr>	
	>b <cr><lf></lf></cr>	
	U <cr><lf>or</lf></cr>	Set the angle format to 0 to 359.9999
	u <cr><lf> or</lf></cr>	degrees.
	>U <cr><lf></lf></cr>	
	>u <cr><lf></lf></cr>	
GET Command	G <cr><lf>or</lf></cr>	Queues the commands until the GET but
	g <cr><lf>or</lf></cr>	command is received.
	>G <cr><lf>or</lf></cr>	
	>g <cr><lf></lf></cr>	

Assert SRQ	V <cr><lf> or</lf></cr>	Asserts SRQ when data is stable.
	v <cr><lf>or</lf></cr>	
	>V <cr><lf> or</lf></cr>	
	>v <cr><lf></lf></cr>	

# 3.5 API-8810 SR103 (Legacy)

The API-8810 SR103 language is only support via the IEEE-488.1. The language is available to provide backwards compatibility to the 8810 SR103 units. Only the features that were available for the 8810 SR103 are supported with this language.

Function	Syntax	Comments
Track/Latch (Hold)	Serial Poll Status Byte	Queries the track/latch state of the
Angle		channel.
	I <cr><lf>or</lf></cr>	Set the latch state for the active channel.
	i <cr><lf>or</lf></cr>	
	>I <cr><lf>or</lf></cr>	
	>i <cr><lf></lf></cr>	
	F <cr><lf> or</lf></cr>	Set the track state for the active channel.
	f <cr><lf>or</lf></cr>	
	>F <cr><lf> or</lf></cr>	
	>f <cr><lf></lf></cr>	
Channel Select	S <cr><lf>or</lf></cr>	If Channel 1 Input is set for "Front
	s <cr><lf> or</lf></cr>	Panel", this will set the Signal Mode to
	>S <cr><lf>or</lf></cr>	SYNCHRO. Channel 1 is set as the
	>s <cr><lf> or</lf></cr>	active channel.
	1 <cr><lf> or</lf></cr>	If Channel Input is set for "Back
	>1 <cr><lf></lf></cr>	Connector" the Signal Mode
		configuration is not modified. Channel 1
		is set as the active channel.
	R <cr><lf>or</lf></cr>	If Channel 1 Input is set for "Front
	r <cr><lf>or</lf></cr>	Panel", this will set the Signal Mode to
	>R <cr><lf>or</lf></cr>	RESOLVER. Channel 1 is set as the
	>r <cr><lf> or</lf></cr>	active channel.
	2 <cr><lf>or</lf></cr>	If Channel Input is set for "Back
	>2 <cr><lf></lf></cr>	Connector" the Signal Mode
		configuration is not modified. Channel 2
	10	is set as the active channel.
Angle Display Format	B <cr><lf> or</lf></cr>	Set the angle format to +/-180 degrees.
	b <cr><lf>or</lf></cr>	
	>B <cr><lf>or</lf></cr>	
	>b <cr><lf></lf></cr>	9 . 1 . 1 . 6
	U <cr><lf>or</lf></cr>	Set the angle format to 0 to 359.9999
	u <cr><lf>or</lf></cr>	degrees.
	>U <cr><lf></lf></cr>	
Darrian II.a On Duaget	>u <cr><lf></lf></cr>	Deserts the device to govern up on 1t
Power-Up Or Preset	P <cr><lf>or</lf></cr>	Resets the device to power-up or last
	p <cr><lf>or</lf></cr>	saved configuration.
	>P <cr><lf>or</lf></cr>	
	>p <cr><lf></lf></cr>	

# 3.7 API-8810 HSR202 (Legacy)

The API-8810 HSR202 language is only support via the IEEE-488.1. The language is available to provide backwards compatibility to the 8810 HSR202 units. Only the features that were available for the 8810 HSR202 are supported with this language.

Function	Syntax	Comments
Track/Latch (Hold) Angle	Serial Poll Status Byte	Queries the track/latch state of the channel.
	I <cr><lf> or i<cr><lf> or &gt;I<cr><lf> or &gt;i<cr><lf> or &gt;i<cr><lf></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr>	Set the latch state for the active channel.
	F <cr><lf> or f<cr><lf> or &gt;F<cr><lf> or &gt;f<cr><lf> or &gt;f<cr><lf></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr>	Set the track state for the active channel.
Channel Select	S <cr><lf> or s<cr><lf> or &gt;S<cr><lf> or &gt;s<cr><lf> or &gt;s<cr><lf></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr>	If Channel 1 Input is set for "Front Panel", this will set the Signal Mode to SYNCHRO. Channel 1 is set as the active channel.  If Channel Input is set for "Back Connector" the Signal Mode configuration is not modified. Channel 1 is set as the active channel.
	R <cr><lf> or r<cr><lf> or &gt;R<cr><lf> or &gt;r<cr><lf></lf></cr></lf></cr></lf></cr></lf></cr>	If Channel 1 Input is set for "Front Panel", this will set the Signal Mode to RESOLVER. Channel 1 is set as the active channel.  If Channel Input is set for "Back Connector" the Signal Mode configuration is not modified. Channel 2 is set as the active channel.
Power-Up Or Preset	P <cr><lf> or p<cr><lf> or &gt;P<cr><lf> or &gt;p<cr><lf> or &gt;p<cr><lf></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr>	Resets the device to power-up or last saved configuration.

# 3.8 API-8810 HSR203 (Legacy)

The API-8810 HSR203 language is only support via the IEEE-488.1. The language is available to provide backwards compatibility to the 8810 HSR203 units. Only the features that were available for the 8810 HSR203 are supported with this language.

Function	Syntax	Comments
Track/Latch (Hold) Angle	Serial Poll Status Byte	Queries the track/latch state of the channel.
7 9-0	I <cr><lf> or i<cr><lf> or &gt;I<cr><lf> or</lf></cr></lf></cr></lf></cr>	Set the latch state for the active channel.
	>i <cr><lf></lf></cr>	
	F <cr><lf>or</lf></cr>	Set the track state for the active channel.
	f <cr><lf> or &gt;F<cr><lf> or &gt;f<cr><lf></lf></cr></lf></cr></lf></cr>	
Channel Select	S <cr><lf> or s<cr><lf> or &gt;S<cr><lf> or &gt;s<cr><lf> or 1<cr><lf> or 1<cr><lf> or &gt;1<cr><lf> or &gt;r<cr><lf> or &gt;R<cr><lf> or &gt;R<cr><lf> or &gt;R<cr><lf> or &gt;r<cr><lf> or &gt;r<cr><lf> or &gt;r<cr><lf> or</lf></cr></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr>	If Channel 1 Input is set for "Front Panel", this will set the Signal Mode to SYNCHRO. Channel 1 is set as the active channel.  If Channel Input is set for "Back Connector" the Signal Mode configuration is not modified. Channel 1 is set as the active channel.  If Channel 1 Input is set for "Front Panel", this will set the Signal Mode to RESOLVER. Channel 1 is set as the active channel.  If Channel Input is set for "Back Channel Input is set for "Back
	>2 <cr><lf></lf></cr>	Connector" the Signal Mode configuration is not modified. Channel 2 is set as the active channel.
Power-Up Or Preset	P <cr><lf> or p<cr><lf> or &gt;P<cr><lf> or &gt;p<cr><lf> or &gt;p<cr><lf></lf></cr></lf></cr></lf></cr></lf></cr></lf></cr>	Resets the device to power-up or last saved configuration.

### 3.9 API-8810 MATE/CIIL (Legacy)

The API-8810 MATE/CIIL language is only support via the IEEE-488.1. The language is available to provide backwards compatibility to the 8810 units with MATE/CIIL support. Only the features that were available for the 8810 MATE/CIIL are supported with this language. Please contact the manufacture if MATE/CIIL support is needed.

#### 4 API-8810A USB Protocol

bool USB WriteMsg(char\* szMsg, bool bExpectReply, char\*pszReply)

The 8810A USB interface supports only the API-8810A Language. Sending commands via the USB interface require the following protocol:

Number of Bytes to be sent	Command ID (8810 (i.e. 0x226A)	Data
(2 bytes)	(2 bytes)	

The following is code snippets from the API8810ADII (USBComm.cpp) that makes calls to the Cypress CyAPI.lib file to sending commands to the 8810A:

```
bool bSuccess = false;
unsigned short usTotalBytes = (unsigned short)strlen(szMsg) + 4; // Length of Message
                                                                // + 2 bytes for Bytes sent
                                                                 // + 2 bytes for Command
unsigned short usCommand = 0x226A;
                                                                 // 8810 (0x226A) Command
     szData[256];
char
      nDataCnt = 0;
LONG BytesToRead = 0;
byte loByte, hiByte;
//***********
// Format data to be sent
// Protocol:
//
     (16 bits) Number of bytes to be sent
//
       (16 bits) Command ID (0x226A) for 8810
       szMsg - data message
// Low byte of Total Bytes to send
loByte = (byte) (usTotalBytes & 0x00FF);
// High byte of Total Bytes to send
hiByte = (byte) (usTotalBytes >> 8);
szData[nDataCnt++] = loByte;
szData[nDataCnt++] = hiByte;
// Low byte of Command
loByte = (byte) (usCommand & 0x00FF);
// High byte of Command
hiByte = (byte) (usCommand >> 8);
szData[nDataCnt++] = loByte;
szData[nDataCnt++] = hiByte;
// Message Data
for (int i = 0; i < (int) strlen(szMsg); i++)
  szData[nDataCnt++] = szMsq[i];
if (glb pUSBDevice)
  if(glb pUSBDevice->IsOpen())
     short numOfTries = 0;
     do
         // Write Data Message
        if (glb pUSBDevice->BulkOutEndPt)
           if (!glb pUSBDevice->BulkOutEndPt->XferData((PUCHAR)&szData, nDataCnt))
```

```
{
              ReinitUSB();
              break;
           }
        }
        // Get Reply if one is expected
        if (bExpectReply)
          if (glb pUSBDevice->BulkInEndPt)
              // Read data (note, max returned from Cypress USB is 64 bytes
              BytesToRead = 64;
             unsigned char aReceiveBuffer[64];
              for (int i = 0; i < 64; i++)
                 aReceiveBuffer[i] = 0;
              glb pUSBDevice->BulkInEndPt->TimeOut = 10000; // 10 second timeout
              bSuccess = glb pUSBDevice->BulkInEndPt->XferData(aReceiveBuffer, BytesToRead);
              numOfTries++;
              if(!bSuccess)
                  Wait(500);
               else
                  strcpy(pszReply, (char *)aReceiveBuffer);
               }
           else
              bSuccess = true;
         else
            bSuccess = true;
      }while((!bSuccess) && (numOfTries < 2));</pre>
   else
      ReinitUSB();
return bSuccess;
```

#### 5 API-8810A Ethernet Protocol

The 8810A Ethernet interface supports only the API-8810A Language. Sending commands via the Ethernet interface requires the creation and connection via a TCP/IP socket.

The following code snippet, <code>CreateClientSocket()</code> from the API8810ADII (Ethernet.cpp) makes calls to the Winsock API to create and connect a TCP/IP socket to send commands to the 8810A. Note the code utilizes the <code>PingHost()</code> call to make sure that the IP address specified for the 8810A is reachable before attempting to create the socket. This avoids waiting for the socket timeout in the <code>connect()</code> call if the device is not reachable. The code snippet, <code>CloseClientSocket()</code> closes the socket connection.

```
int CreateClientSocket(char *pszIPAddr, int nPort, SOCKET* s)
  WSADATA
               wsaData;
   SOCKET
                sock;
   SOCKADDR IN ServerAddr;
   int result:
   /* Before trying to make a connection to the server, ping it to make sure it's reachable */
   result = PingHost(pszIPAddr);
   if (result != 0)
      return ETHER CANNOT ESTABLISH CONNECTION;
   // Initialize Winsock version 2.2
   WSAStartup (MAKEWORD (2,2), &wsaData);
   // Create a new socket to make a TCP client connection
   sock = socket(AF_INET, SOCK_STREAM, IPPROTO TCP);
   setsockopt( sock, SOL_SOCKET, SO_RCVTIMEO, (char*)&RECEIVE_TIMEOUT, sizeof(int) );
   setsockopt( sock, SOL SOCKET, SO SNDTIMEO, (char*) & SEND TIMEOUT, sizeof(int) );
   // set to no delay to insure quick ack
   result = setsockopt( sock, IPPROTO TCP, TCP NODELAY, (char*)&NO DELAY, sizeof(int) );
   // Setup a SOCKADDR IN structure that will be used to connect
   // to the listening server on the Port.
   ServerAddr.sin family = AF INET;
   ServerAddr.sin_port = htons(nPort);
   ServerAddr.sin addr.s addr = inet addr(pszIPAddr);
   // Make a connection to the server with socket sock
   connect(sock, (const struct sockaddr *) &ServerAddr, sizeof(ServerAddr));
   *s = sock;
   Socket = sock; // put it into global socket
  return ETHER SUCCESS;
int CloseClientSocket(SOCKET s)
 closesocket(s):
 WSACleanup();
 return ETHER SUCCESS;
```

After a socket connection is made to the 8810A, device log-in is required. 8810A Ethernet login is accomplished by sending "NAII\r\n" command via the Ethernet connection to the 8810A.

The following code snippets, <code>Ethernet\_WriteMsg()</code>, <code>SendEthernetMsg()</code> and <code>ReadEthernetMsg()</code> from the API8810ADII (Ethernet.cpp) makes calls to the Winsock API to send and receive messages to and from the 8810A.

```
1500
#define MSG MAX SIZE
                                        /* Maximum number of bytes to send */
#define RECV MSG MAX SIZE
                            1500
                                       /* Maximum number of bytes that can be read */
bool Ethernet_WriteMsg(SOCKET s, char* szMsg, bool bExpectReply, char* pszReply)
  bool bSuccess = false;
  char aReceiveBuffer[RECV MSG MAX SIZE];
  int nBytesRead = 0;
   if (SendEthernetMsg(s, &szMsg[0], strlen(szMsg)) == ETHER SEND ERROR)
     return bSuccess;
   if (bExpectReply)
      if (ReadEthernetMsg(s, RECV MSG MAX SIZE, aReceiveBuffer, &nBytesRead) == ETHER RECV ERROR)
         return bSuccess;
      strncpy(pszReply, (char *)aReceiveBuffer, nBytesRead);
  bSuccess = true;
  return bSuccess;
int SendEthernetMsg(SOCKET s, char *pszMessage, int nMessageLen)
  int ret;
  char sendbuff[MSG MAX SIZE];
  int nLeft;
   int nIndex;
  int status = 0;
   // Copy the data to be sent to the buffer
   for (nIndex = 0; nIndex < nMessageLen; nIndex++)</pre>
     sendbuff[nIndex] = pszMessage[nIndex];
   nLeft = nMessageLen;
  nIndex = 0;
   while (nLeft > 0)
     ret = send(s, &sendbuff[nIndex], nLeft, 0);
     // It seems we sent some data
      if (ret != SOCKET ERROR)
        nLeft -= ret;
        nIndex += ret;
      // got SOCKET ERROR
      else
        status = ETHER SEND ERROR;
      }
   }
   if (nLeft > 0)
     status = ETHER SEND ERROR; /* ERROR */
     status = ETHER SUCCESS; /* SUCCESS */
   return status;
```

```
int ReadEthernetMsg(SOCKET s, int nMessageLenToBeRead, char *pszMessage, int *nMessageLen)
  int ret;
  int nLeft;
  int nIndex;
int status = 0;
  nLeft = nMessageLenToBeRead;
  nIndex = 0;
  while (nLeft > 0)
     ret = recv(s, pszMessage, nLeft, 0);
     // It seems we got some data
     if (ret != SOCKET ERROR)
        nLeft -= ret;
        nIndex += ret;
        pszMessage += ret;
        // We don't know the exact size of each message
         // for API we know that it won't exceed RECV_MSG_MAX_SIZE bytes
         nMessageLenToBeRead = nLeft;
         nLeft = 0;
      // got SOCKET ERROR
     else
      {
         status = ETHER RECV ERROR;
        break;
       }
    }
   if (nIndex > 0)
   {
      *nMessageLen = nIndex;
      status = ETHER SUCCESS; /* SUCCESS */
     status = ETHER_RECV_ERROR; /* ERROR */
   return status;
```

#### 6 API-8810A DLL


A dynamic link library (DLL) written in C, compiled under Microsoft Visual .NET 2010 has been included in the software package to provide a program interface that handles the language syntax to communicate with the unit. The function lists provided in this Dynamic-link library (DLL) is described in *Function Reference Manual for 8810A*.


Revision 3.0.0.2


## 7 API-8810A Soft Panel Program


A Soft Panel application written in C#, compiled under Microsoft Visual .NET 2010 that invokes the routines in the API-8810A Dll has been included in the software package. Note, the Microsoft .NET Framework 1.1 must be installed on your machine prior to running the Soft Panel application. The .NET Framework Version 1.1 Redistributable Package can be downloaded from the Microsoft Web site:


http://www.microsoft.com/downloads


















In this screen, the Read button will invoke the Multiple Channel Query routines to retrieve the data for both channels using the query command that returns data for channels.



Commands sent to the API 8810A as well as the results from performing a call to the API8810A Dll's API8810A\_GetErrors() method to retrieve any messages from the Error Queue.

Revision 3.0.0.2

## 8 Cypress USB Driver Installation

In order to communicate with API 8810A unit via the USB 2.0 interface, the Cypress USB Driver must be installed. Please refer to the document labeled "Cypress USB Installation" for detailed instruction on how to install the driver on your Windows PC.

# **Revision History**

Revision ID	Revision Date	Description	Author
1.0.0.0	Jul 27, 2006	Initial Release	gc
1.0.0.1	Aug 4, 2006	Added Language Independent Commands section (3.2). Added remote programmability support to configure 8810A's Bandwidth, Language, and Channel 1 Front/Back settings. Added USB Protocol definition.	gc
2.0.0.2	Dec 21, 2007	Added remote programmability support for averaging, limit testing, data buffer control, multiple channel data retrieval. Updated screen shots for Soft Panel application. Removed function reference in API-8810A Dll. The functions specified in the Dll have been moved to the Function Reference Manual.	gc
2.0.0.3	May 30, 2008	Added remote programmability support for periodic calibration.	gc
2.0.0.4	July 31, 2008	Modified the API Soft Panel Screen (p42) to include the additional button that allows the user to read and log the channels' angle data directly to the specified file	gc
2.0.0.15	Mar 30, 2009	Added analog display mode, ability to adjust resolution of angle display, output angles in radians, mil-radians, angle offset option and recall of channel display (ch 1, ch 2 or dual) after power off.	gc
2.0.0.18	Oct 23, 2009	Updated soft panel to support Internal Reference Overcurrent State and reset Overrcurrent. Only supported with Function DSP revision 100 or greater.	gc
2.0.0.19	Mar 17, 2010	Updated the Angle Data Output format for 8810 SR103, HSR202 and HSR203 legacy systems. These do not return a '<' character before the angle digits like the 8810 NATIVE.	gc
2.0.0.20	Apr 08, 2010	Added 8810FX2 mode to support automatic setup for the 8810A to the 8810-FX2 configuration	gc
2.0.0.21	Jul 1, 2010	Fixed problem with the IEEE address and Ethernet addresses getting set to factory default values for the *RST? and APICMD RSTFRAM commands.	gc

		Added ability to remotely change the API-	
		8810A screen display.	
		Updated the Device Manager screen to reflect	
		the new revision (3.4.1.20) of the Cypress	
		USB driver. This driver supports multiple	
		Cypress USB Devices.	
3.0.0.1	Oct 3, 2012	Updated the Cypress USB Driver Installation	gc
		section to refer to the "Cypress USB	
		Installation" document.	
		API8810A Dll and API8810A Soft Panel	
		Program are built with Microsoft Visual	
		.NET 2010.	
3.0.0.2	Nov 16, 2012	No changes to API. Updated document	gc
		revision to correspond to SSK release 3.0.0.2	
		which changed the Windows XP and	
		Windows 7 folder names for the Cypress	
		USB Driver.	