

Function Reference Manual for 8810A

Two Synchro/Resolver Measurement and One optional Reference supply

Function Reference Manual for 8810A



Table of Contents

I	Intro	duction	5
2	API-	8810A Connect/Disconnect Routines	11
	2.1	API8810A_ConnectViaIEEE	11
	2.2	API8810A_ConnectViaUSB	12
	2.3	API8810A_ConnectViaEthernet	16
	2.4	API8810A_DisconnectIEEE	16
	2.5	API8810A_DisconnectUSB	17
	2.6	API8810A_DisconnectEthernet	
	2.7	API8810A_GetAPI8810AUSBDeviceCnt	17
	2.8	API8810A_GetAPI8810ADeviceIDN	18
3	API-	8810A Channel Routines	19
	3.1	API8810A_SetAPITrackHold	19
	3.2	API8810A_GetAPITrackHold	19
	3.3	API8810A_SetAPISignalMode	20
	3.4	API8810A_GetAPISignalMode	20
	3.5	API8810A_SetAPIReferenceSrc	21
	3.6	API8810A_GetAPIReferenceSrc	22
	3.7	API8810A_SetAPIRatio	22
	3.8	API8810A_GetAPIRatio	23
	3.9	API8810A_SetAPIAutoBandwidth	24
	3.10	API8810A_SetAPIBandwidth	24
	3.11	API8810A_GetAPIBandwidth	25
	3.12	API8810A_GetAPIAngle	25
	3.13	API8810A_GetAPIAvgAngle	26
	3.14	API8810A_GetAPIVelocity	26
	3.15	API8810A_GetAPILineLineVolt	27
	3.16	API8810A_GetAPINullVolt	28
	3.17	API8810A_GetAPIRefVolt	28
	3.18	API8810A_GetAPIRefFreq	29
	3.19	API8810A_SetAPIAvgState	29
	3.20	API8810A_GetAPIAvgState	30
	3.21	API8810A_SetAPIAvgRate	30
	3.22	API8810A_GetAPIAvgRate	31
	3.23	API8810A_SetAPIAngLimitState	32
	3.24	API8810A_GetAPIAngLimitState	32
	3.25	API8810A_SetAPIAngLimitCompare	33
	3.26	API8810A_GetAPIAngLimitCompare	33
	3.27	API8810A_SetAPIAngUpperLimit	34
	3.28	API8810A_GetAPIAngUpperLimit	35
	3.29	API8810A_SetAPIAngLowerLimit	
	3.30	API8810A_GetAPIAngLowerLimit	
	3.31	API8810A_SetAPIAngLimitErrorStep	36
	3.32	API8810A_GetAPIAngLimitErrorStep	

Revision 3.0.0.2

	3.33	API8810A_SetAPIDAOutput	38
	3.34	API8810A_GetAPIDAOutput	
	3.35	API8810A_SetAPIDAUpperLimit	39
	3.36	API8810A_GetAPIDAUpperLimit	
	3.37	API8810A_SetAPIDALowerLimit	40
	3.38	API8810A_GetAPIDALowerLimit	41
	3.39	API8810A_SetAPIDAUpperVoltage	41
	3.40	API8810A_GetAPIDAUpperVoltage	42
	3.41	API8810A_SetAPIDALowerVoltage	42
	3.42	API8810A_GetAPIDALowerVoltage	43
	3.43	API8810A_SetAPIDisplayAngDiffState	44
	3.44	API8810A_GetAPIDisplayAngDiffState	44
	3.45	API8810A_GetAPIAngleDiff	45
4	API-	8810A Multiple Channel Query Routines	46
	4.1	API8810A_GetAPIAngles	46
	4.2	API8810A_GetAPIAvgStates	46
	4.3	API8810A_GetAPIAvgAngles	47
	4.4	API8810A_GetAPIBandwidths	48
	4.5	API8810A_GetAPISignalModes	
	4.6	API8810A_GetAPIRatios	
	4.7	API8810A_GetAPIReferenceSrcs	
	4.8	API8810A_GetAPITrackHolds	50
	4.9	API8810A_GetAPIAngLimitStates	51
	4.10	API8810A_GetAPIVelocities	
	4.11	API8810A_GetAPILineLineVolts	
	4.12	API8810A_GetAPINullVolts	53
	4.13	API8810A_GetAPIRefVolts	
	4.14	API8810A_GetAPIRefFreqs	
5	API-	8810A Internal Reference Routines	
	5.1	API8810A_SetIntRefFreq	55
	5.2	API8810A_GetIntRefFreq	
	5.3	API8810A_SetIntRefVolt	
	5.4	API8810A_GetIntRefVolt	
	5.5	API8810A_SetIntRefOutputState	
	5.6	API8810A_GetIntRefOutputState	
	5.7	API8810A_GetIntRefOverCurrentState	
	5.8	API8810A_ResetIntRefOverCurrent	
6		8810A Command Routines	
	6.1	API8810A_PerformGetID	
	6.2	API8810A_Reset	
	6.3	API8810A_GetErrors	
7		8810A Configuration Routines	
	7.1	API8810A_GetIEEELang.	
	7.2	API8810A_SetIEEELang	
	7.3	API8810A_GetCommState	
	7.4	API8810A_GoToLocal	64

	7.5	API8810A_SetLocalLockout	64
	7.6	API8810A_SetRemoteUSB	65
	7.7	API8810A_SetRemoteEthernet	65
	7.8	API8810A_SetRemoteIEEE	66
	7.9	API8810A_SetRemoteJ1	66
	7.10	API8810A_SetAngleDisplayFormat	67
	7.11	API8810A_GetAngleDisplayFormat	67
	7.12	API8810A_SetCh1Input	68
	7.13	API8810A_GetCh1Input	69
	7.14	API8810A_SetTouchscreenState	69
	7.15	API8810A_GetTouchscreenState	70
	7.16	API8810A_SetDisplayState	
	7.17	API8810A_GetDisplayState	71
	7.18	API8810A_ResetDefaultValues	
8	AP	PI-8810A Calibration Routines	
	8.1	API8810A_GetCalState	73
	8.2	API8810A_Calibrate	73
	8.3	API8810A_SetAPIPeriodicCalState	74
	8.4	API8810A_GetAPIPeriodicCalState	
9	AP	PI-8810A Buffer Routines	
	9.1	API8810A_GetSampleRate	76
	9.2	API8810A_SetSampleRate	
	9.3	API8810A_GetSampleType	77
	9.4	API8810A_SetSampleType	78
	9.5	API8810A_GetPlotChan	
	9.6	API8810A_SetPlotChan	
	9.7	API8810A_GetAngleErrStep	
	9.8	API8810A_SetAngleErrStep	80
	9.9	API8810A_GetLowerRange	
	9.10	API8810A_SetLowerRange	
	9.11	API8810A_GetUpperRange	
	9.12	API8810A_SetUpperRange	
	9.13	API8810A_GetRecordingState	
	9.14	API8810A_SetRecordingState	
	9.15	API8810A_GetBufferCnt	
	9.16	API8810A_GetBufferData	
1(API-8810A Miscellaneous Routines	
	10.1	API8810A_MaxRetry	
	10.2	API8810A_LastCmdSent	
	10.3	API8810A_WriteCommand	
	10.4	API8810A_QueryCommand	
11		Appendix A – API8810ADll Constant Values	
12	2	Appendix B- Error Codes	90

Introduction 1

This document lists the functions and describes the purpose, format, input and output parameters, and possible errors for each function.

Reference Documentation

For information about the operation of this instrument please refer to the Operation Manual for Model 8810A.

For information about general programming information please refer to the *Programmer's* Reference Guide for 8810A.

Reference CD

For electronic copies of the 8810A documentation, API-8810A Soft Panel application program, and source code for API-8810ADII and Soft Panel application please refer to the 8810A Product CD.

Revision 3.0.0.2

API-8810A Connect/Disconnect Routines Sets up and opens the connection to communicate to the 8810A via IEEE. The following IEEE languages are supported: • API-8810A Native • API-8810 Native (Legacy) • API-8810 SR103 (Legacy) • API-8810 HSR202 (Legacy) • API-8810 HSR203 (Legacy) • API-8810 Native FX2 (Legacy) • API-8810 Native FX2 (Legacy) API-8810 Native FX2 (Legacy) Sets up and opens the connection to communicate to the 8810A via USB. API-8810A DisconnectViaEthernet API-8810A DisconnectUSB API-8810A DisconnectUSB Closes the IEEE connection. API-8810A DisconnectUSB API-8810A DisconnectEthernet Closes the USB connection. API-8810A DisconnectEthernet API-8810A DisconnectEthernet Closes the Ethernet connection. API-8810A GetAPI-8810AUSBDeviceCnt Between the following IEEE languages are supported: API-8810A Native API-8810 Native FX2 (Legacy) Closes the connection to communicate to the 8810A via USB. Closes the USB connection to communicate to the 8810A via Ethernet. API-8810A DisconnectUSB API-8810A DisconnectUSB Closes the USB connection. API-8810A GetAPI-8810AUSBDeviceCnt API-8810A GetAPI-8810ADeviceIDN() routine to determine the device numbers for 8810A devices.
8810A via IEEE. The following IEEE languages are supported: • API-8810A Native • API-8810 Native (Legacy) • API-8810 SR103 (Legacy) • API-8810 HSR202 (Legacy) • API-8810 HSR203 (Legacy) • API-8810 Native FX2 (Legacy) • API-8810 Native FX2 (Legacy) API-8810 Native FX2 (Legacy) Sets up and opens the connection to communicate to the 8810A via USB. API8810A DisconnectViaEthernet API8810A DisconnectUSE Closes the IEEE connection. API8810A DisconnectEEE Closes the USB connection. Closes the USB connection. API8810A DisconnectEthernet Closes the Ethernet connection. API8810A GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
supported: API-8810A Native API-8810 Native (Legacy) API-8810 SR103 (Legacy) API-8810 HSR202 (Legacy) API-8810 HSR203 (Legacy) API-8810 HSR203 (Legacy) API-8810 Native FX2 (Legacy) API-8810 Native FX2 (Legacy) Sets up and opens the connection to communicate to the 8810A via USB. API-8810A DisconnectViaEthernet Sets up and opens the connection to communicate to the 8810A via Ethernet. Closes the IEEE connection. API-8810A DisconnectUSB Closes the USB connection. API-8810A DisconnectEthernet Closes the Ethernet connection. API-8810A GetAPI-8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API-8810A_GetAPI-8810ADeviceIDN() routine to
 API-8810A Native API-8810 Native (Legacy) API-8810 SR103 (Legacy) API-8810 HSR202 (Legacy) API-8810 HSR203 (Legacy) API-8810 Native FX2 (Legacy) API-8810 Native FX2 (Legacy) Sets up and opens the connection to communicate to the 8810A via USB. API8810A DisconnectViaEthernet API8810A DisconnectUSB API8810A DisconnectUSB API8810A DisconnectEthernet Closes the USB connection. API8810A DisconnectEthernet Closes the Ethernet connection. API8810A GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
 API-8810 Native (Legacy) API-8810 SR103 (Legacy) API-8810 HSR202 (Legacy) API-8810 HSR203 (Legacy) API-8810 Native FX2 (Legacy) API-8810 Native FX2 (Legacy) API-8810 Native FX2 (Legacy) API-8810 Native FX2 (Legacy) Sets up and opens the connection to communicate to the 8810A via USB. API8810A DisconnectIEEE Closes the IEEE connection. API8810A DisconnectEthernet Closes the USB connection. API8810A DisconnectEthernet Closes the Ethernet connection. API8810A GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
 API-8810 SR103 (Legacy) API-8810 HSR202 (Legacy) API-8810 HSR203 (Legacy) API-8810 Native FX2 (Legacy) API-8810 Native FX2 (Legacy) Sets up and opens the connection to communicate to the 8810A via USB. API8810A DisconnectIEEE Closes the IEEE connection. API8810A DisconnectUSB Closes the USB connection. API8810A DisconnectEthernet API8810A DisconnectEthernet API8810A GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
 API-8810 HSR202 (Legacy) API-8810 HSR203 (Legacy) API-8810 Native FX2 (Legacy) API8810A_ConnectViaUSB Sets up and opens the connection to communicate to the 8810A via USB. API8810A_DisconnectIEEE API8810A_DisconnectUSB Closes the IEEE connection. API8810A_DisconnectEthernet Closes the USB connection. API8810A_DisconnectEthernet API8810A_GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
 API-8810 HSR203 (Legacy) API-8810 Native FX2 (Legacy) API-8810 Native FX2 (Legacy) Sets up and opens the connection to communicate to the 8810A via USB. API8810A ConnectViaEthernet Sets up and opens the connection to communicate to the 8810A via Ethernet. API8810A DisconnectIEEE Closes the IEEE connection. API8810A DisconnectEthernet Closes the USB connection. API8810A GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
API8810A_ConnectViaUSB Sets up and opens the connection to communicate to the 8810A via USB. API8810A_ConnectViaEthernet Sets up and opens the connection to communicate to the 8810A via Ethernet. API8810A_DisconnectIEEE Closes the IEEE connection. API8810A_DisconnectUSB Closes the USB connection. API8810A_DisconnectEthernet Closes the Ethernet connection. API8810A_GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
API8810A_ConnectViaUSB API8810A_ConnectViaEthernet Sets up and opens the connection to communicate to the 8810A via USB. Sets up and opens the connection to communicate to the 8810A via Ethernet. API8810A_DisconnectIEEE API8810A_DisconnectUSB API8810A_DisconnectEthernet API8810A_DisconnectEthernet Closes the USB connection. API8810A_GetAPI8810AUSBDeviceCnt API8810A_GetAPI8810AUSBDeviceCnt API8810A_GetAPI8810ADeviceIDN() routine to
API8810A ConnectViaEthernet Sets up and opens the connection to communicate to the 8810A via Ethernet. API8810A DisconnectIEEE Closes the IEEE connection. API8810A DisconnectUSB Closes the USB connection. API8810A DisconnectEthernet Closes the Ethernet connection. API8810A GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
API8810A_ConnectViaEthernet Sets up and opens the connection to communicate to the 8810A via Ethernet. Closes the IEEE connection. API8810A_DisconnectUSB Closes the USB connection. Closes the Ethernet connection. API8810A_DisconnectEthernet API8810A_GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
8810A via Ethernet. API8810A DisconnectIEEE Closes the IEEE connection. API8810A DisconnectUSB Closes the USB connection. API8810A DisconnectEthernet Closes the Ethernet connection. API8810A GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
API8810A DisconnectUSB Closes the USB connection. API8810A DisconnectEthernet Closes the USB connection. Closes the Ethernet connection. API8810A GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
API8810A DisconnectUSB API8810A DisconnectEthernet Closes the USB connection. Closes the Ethernet connection. Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
API8810A DisconnectEthernet Closes the Ethernet connection. API8810A GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
API8810A_GetAPI8810AUSBDeviceCnt Scan the USB Ports for the number of Cypress USB Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
Devices. Note, after calling this function, call API8810A_GetAPI8810ADeviceIDN() routine to
API8810A_GetAPI8810ADeviceIDN() routine to
API8810A_GetAPI8810ADeviceIDN Performs an IDN query on the Cypress USB Device and
determines if the device being queried is an 8810A
device. If it is, the IDN response which includes
manufacture, model, and serial number is returned.
API-8810A Channel Routines
API8810A_SetAPITrackHold Sets the channel's track/latch (hold) state.
API8810A_GetAPITrackHold Gets the channel's track/latch (hold) state.
API8810A_SetAPISignalMode Sets the channel's signal mode (SYN/RSL).
API8810A_GetAPISignalMode Gets the channel's signal mode.
API8810A_SetAPIReferenceSrc Sets the channel's reference source mode (INT/EXT).
API8810A_GetAPIReferenceSrc Gets the channel's reference source mode.
API8810A_SetAPIRatio Sets the channel's ratio value.
API8810A_GetAPIRatio Gets the channel's ratio value.
API8810A_SetAPIAutoBandwidth Sets the channel's bandwidth to "auto" mode.
API8810A_SetAPIBandwidth Sets the channel's bandwidth to "override" mode and set
the channel's bandwidth value.
API8810A_GetAPIBandwidth Gets the channel's bandwidth mode and bandwidth
value.
API8810A_GetAPIAngle Gets the channel's angle value.
API8810A GetAPIAvgAngle Gets the channel's angle average value.
API8810A GetAPIVelocity Gets the channel's angle velocity value.
API8810A GetAPILineLineVolt Gets the channel's line-to-line voltage value.
API8810A GetAPINullVolt Gets the channel's null voltage value.
API8810A GetAPIRefVolt Gets the channel's reference voltage value.

API8810A_GetAPIRefFreq	Gets the channel's reference frequency value.
API8810A_SetAPIAvgState	Sets the channel's angle averaging mode.
	<u> </u>
API8810A_GetAPIAvgState	Gets the channel's angle averaging mode.
API8810A_SetAPIAvgRate	Sets the channel's angle averaging rate.
API8810A_GetAPIAvgRate	Gets the channel's angle averaging rate.
API8810A_SetAPIAngLimitState	Sets the channel's angle limit testing mode.
API8810A GetAPIAngLimitState	Gets the channel's angle limit testing mode.
API8810A SetAPIAngLimitCompare	Sets the channel's angle limit testing comparison mode.
API8810A GetAPIAngLimitCompare	Gets the channel's angle limit testing comparison mode.
API8810A_SetAPIAngUpperLimit	Sets the channel's upper angle limit value for angle limit
	testing.
API8810A_GetAPIAngUpperLimit	Gets the channel's upper angle limit value for angle limit
	testing.
API8810A_SetAPIAngLowerLimit	Sets the channel's lower angle limit value for angle limit
	testing.
API8810A_GetAPIAngLowerLimit	Gets the channel's lower angle limit value for angle limit
	testing.
API8810A_SetAPIAngLimitErrorStep	Sets the channel's angle step value for angle error
	comparison for angle limit testing.
API8810A GetAPIAngLimitErrorStep	Gets the channel's angle step value for angle error
	comparison for angle limit testing.
API8810A_SetAPIDAOutput	Sets channel's data type (angle or velocity) to use for DA
	output.
API8810A_GetAPIDAOutput	Gets channel's data type (angle or velocity) to use for
	DA output.
API8810A_SetAPIDAUpperLimit	Sets the channel's upper angle or velocity limit value for
	DA output.
API8810A GetAPIDAUpperLimit	Gets the channel's upper angle or velocity limit value for
TH 1001011 Gett II ID110 pper Emitt	DA output.
API8810A_SetAPIDALowerLimit	Sets the channel's lower angle or velocity limit value for
II 10010/1 DOWN ID/IE/WOLDHING	DA output.
API8810A GetAPIDALowerLimit	Gets the channel's lower angle or velocity limit value for
THEOTOT COUNT ID THOW CITINIT	DA output.
API8810A SetAPIDAUpperVoltage	Sets the channel's voltage value associated with the
11 10010/1 Del/11 iD/10ppci voltage	upper limit value for DA output.
API8810A_GetAPIDAUpperVoltage	Gets the channel's voltage value associated with the
In 10010/1_Oct/11 1D/10 ppci voltage	upper limit value for DA output
API8810A_SetAPIDALowerVoltage	Sets the channel's voltage value associated with the
M 10010A SCIAI IDALUWEI VOItage	lower limit value for DA output.
API8810A GetAPIDALowerVoltage	Gets the channel's voltage value associated with the
AI 10010A OCIAI IDALOWEI VOItage	lower limit value for DA output
ADISSION Set A DIDioplay Ang DiffState	Sets the channel's angle difference display mode.
APISSIOA Cet A PIDioplay And DiffState	
API8810A GetAPIDisplayAngDiffState	Gets the channel's angle difference display mode.
API8810A GetAPIAngleDiff	Gets the angle difference value between Channel 1 and
	Channel 2 input signal.

API-8810A Multiple Channel Query Routines		
API8810A GetAPIAngles	Get both channels' angle values.	
API8810A_GetAPIAvgStates	Get both channels' angle averaging modes and average	
	rates.	
API8810A_GetAPIAvgAngles	Get both channels' angle average values.	
API8810A_GetAPIBandwidths	Get both channels' bandwidth mode and bandwidth	
	values.	
API8810A_GetAPISignalModes	Get both channels' signal modes.	
API8810A_GetAPIRatios	Get both channels' ratio values.	
API8810A_GetAPIReferenceSrcs	Get both channels' reference source modes.	
API8810A_GetAPITrackHolds	Get both channels' track or hold states.	
API8810A GetAPIAngLimitStates	Get both channels' angle limit testing states and	
	comparison modes.	
API8810A GetAPIVelocities	Get both channels' velocity values.	
API8810A GetAPILineLineVolts	Get both channels' line-to-line voltage values.	
API8810A GetAPINullVolts	Get both channels' null voltage values.	
API8810A GetAPIRefVolts	Get both channels' reference voltage values.	
API8810A_GetAPIRefFreqs	Get both channels' reference frequency values.	
<u>API-8810A l</u>	Internal Reference Routines	
API8810A_SetIntRefFreq	Sets the internal reference frequency value.	
API8810A_GetIntRefFreq	Gets the internal reference frequency value.	
API8810A_SetIntRefVolt	Sets the internal reference voltage value.	
API8810A_GetIntRefVolt	Gets the internal reference voltage value.	
API8810A SetIntRefOutputState	Sets the internal reference output state.	
API8810A_GetIntRefOutputState	Gets the internal reference output state.	
API8810A_GetIntRefOverCurrentState	Gets the internal reference over current state.	
API8810A ResetIntRefOverCurrent	Resets the internal reference over current state.	
	0A Command Routines	
API8810A PerformGetID	Gets the Device ID.	
API8810A_Reset	Resets the device.	
API8810A GetErrors	Gets the error message from the error queue.	
<u>API-8810</u>	A Configuration Routines	
API8810A_GetIEEELang	Gets the IEEE Language protocol configured in the	
ADIO010A CatIEEEI and	8810A.	
API8810A_SetIEEELang API8810A GetCommState	Sets the IEEE Language protocol to accept in the 8810A. Gets the communication settings.	
API8810A GoToLocal		
API8810A_Go1oLocal API8810A_SetLocalLockout	Sets the device to Local mode. Sets the device to Local Lockout mode.	
API8810A SetRemoteUSB	Sets the device to Local Lockout mode. Sets the device to Remote USB mode.	
API8810A SetRemoteEthernet	Sets the device to Remote USB mode. Sets the device to Remote Ethernet mode.	
API8810A_SetRemoteIEEE	Sets the device to Remote Ethernet mode. Sets the device to Remote IEEE mode.	
API8810A_SetRemoteJ1	Sets the device to Remote IEEE mode. Sets the device to Remote J1 mode.	
API8810A SetAngleDisplayFormat	Sets the Angle Display Format.	
API8810A_GetAngleDisplayFormat	Gets the Angle Display Format	

API8810A_SetCh1Input	Sets the Channel 1 Input Connector configuration.
	Gets the Channel 1 Input Connector configuration.
API8810A_GetCh1Input API8810A_SetTouchscreenState	Sets the Touch screen mode.
API8810A_GetTouchscreenState	Gets the Touch screen mode.
APISSIOA CatDianlayState	Sets the display to show on the device.
APISSIOA Reget Default Values	Gets the display shown on the device.
API8810A_ResetDefaultValues	Sets the device to the default factory settings. A Calibration Routines
API8810A_GetCalState	Gets the calibration state.
API8810A_Calibrate	Calibrates the 8810A.
API8810A_SetAPIPeriodicCalState	Enables or disables the periodic calibration.
API8810A_GetAPIPeriodicCalState	Gets the periodic calibration state.
	B10A Buffer Routines
API8810A GetSampleRate	Gets the sample rate for data buffering.
API8810A SetSampleRate	Sets the sample rate for data buffering.
API8810A_GetSampleType	Gets the data type to sample for data buffering.
API8810A_SetSampleType	Sets the data type to sample for data buffering.
API8810A_GetPlotChan	Gets the channels to plot on the 8810A chart.
API8810A SetPlotChan	Sets the channels to plot on the 8810A chart.
API8810A GetAngleErrStep	Gets the angle step value for angle error comparison for
	data buffering.
API8810A_SetAngleErrStep	Sets the angle step value for angle error comparison for
	data buffering.
API8810A_GetLowerRange	Gets the expected lower range value for plotting on the
	8810A chart.
API8810A SetLowerRange	Sets the expected lower range value for plotting on the
	8810A chart.
API8810A GetUpperRange	Gets the expected upper range value for plotting on the
	8810A chart.
API8810A_SetUpperRange	Sets the expected upper range value for plotting on the
ADVOCATO A CONTRACTOR OF THE C	8810A chart.
APISSIOA G CR CONTROL	Gets the recording state.
APISSIOA C. P. S. C.	Sets the recording state.
API8810A GetBufferCnt	Gets the number of elements in the 8810A data buffer.
API8810A GetBufferData	Gets the data elements in the 8810A data buffer. Data
	retrieval from the data buffer is available only via the
A DT 9910 A	USB or Ethernet interface.
	Miscellaneous Routines Sets the number of retries for re-sending data after a
API8810A MaxRetry	timeout or problem sending or reading data from device.
	Default value for max retry is 0.
API8810A_LastCmdSent	Returns the last command set to the device by Dll.
API8810A WriteCommand	Sends the freeform command to the 8810A.
API8810A QueryCommand	Sends the freeform command to the 8810A and waits for
211 10010/1 Query Communa	a response.
	a response.

2 API-8810A Connect/Disconnect Routines

The routines in this section handle IEEE, Ethernet and USB communications to the 8810A device.

2.1 API8810A_ConnectVialEEE

Format:

```
_API8810AFUNC int API8810A_ConnectViaIEEE (
   int apiNo,
   int nIEEEAddr,
   int nIEEELang
)
```

Function Description:

This function sets up and opens the connection to communicate to the 8810A via IEEE.

The IEEE supports the following language protocols:

- API-8810A Native
- API-8810 Native (Legacy)
- API-8810 SR103 (Legacy)
- API-8810 HSR202 (Legacy)
- API-8810 HSR203 (Legacy)

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nIEEEAddr - IEEE Address to be used to connect to 8810A. (0-30)
nIEEELang - Language Protocol to be used to communicate via IEEE to 8810A.

8810A Language Types:

API8810ANATIVE
0
IEEE_API8810NATIVE
1
IEEE_API8810SR103
2
IEEE_API8810HSR202
3
IEEE_API8810HSR203
4
IEEE_API8810MATECIIL
5
IEEE API8810FX2
6
```

Return Value:

```
API_SUCCESS - successfully connection via IEEE using specified address and language protocol

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_ADDRS - invalid IEEE Address parameter

API_ERROR_LANG - invalid 8810A Language parameter

API_ERROR_OPEN_API_SESSION - IEEE connection or configuration error
```

References for this function:

This function will make a call to the API8810A_SetIEEELang() routine to force the 8810A device to handle commands in the language specified.

2.2 API8810A ConnectViaUSB

Format:

```
API8810AFUNC int API8810A ConnectViaUSB
  int apiNo,
  int nDeviceNo
```

Function Description:

This function sets up and opens the connection to communicate to the 8810A via USB.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX API) nDeviceNo - Device Number to be used to connect to 8810A. (0-30)

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR USB CONNECTION- USB connection error
```

References for this function:

Prior to calling this function, make calls to the API8810A GetAPI8810AUSBDeviceCnt() routine to determine the number of Cypress USB Devices detected in your system and the API8810A GetAPI8810ADeviceIDN() routine to determine the device number (DeviceNo) associated with the Cypress USB Devices that are connected to 8810A via USB.

Sample Code:

The following sample code is available in the 8810A Software Package under the folder: ..\Driver\Source\API8810AUSBConnect. The sample code is written in C, compiled under Microsoft Visual .NET 2003 and invokes the routines in the API-8810A Dll that has been included in the software package.

```
#include <stdio.h>
#include <stdlib.h>
#include <Windows.h>
#include <Wincon.h>
#define _BUILD_API8810ADLL
#define __WIN32
#include "API8810AD11.h"
/* Prototype definition for the Console Window */
extern WINBASEAPI HWND WINAPI GetConsoleWindow ();
/***************************
 Function:
  Description: Main routine for API8810A USB Connection application.
                 Scan for Cypress USB devices and opens each USB device to
                 determine which one is connected to a 8810A via IDN command.
                 Prompts the user for the USB Endpoint associated with 8810\mbox{A}
                 device and reads and displays the Signal Mode for Channel 1.
                None
  Parameters:
  Return:
                1 if successful.
                -1 if any failure to API8810AD11 calls.
int main()
  HANDLE hWnd;
  COORD bufferSize;
  BOOL bRetry;
  int nStatus;
  int nUSBDeviceCnt;
   int n8810ADeviceCnt;
  char sz8810AIDN[100];
   int i,j;
   /* This keeps track of the array of the Cypress USB Endpoints.
     We are only interested in the ones that are connected to the 8810A
   int aUSB 8810A Endpoints[MAX API];
   BOOL bValidEntry;
   int nConnectEndpoint;
   int nSigMode;
  char buff[10];
   /* Get the console window */
  hWnd = GetConsoleWindow();
   ^{\prime \star} Create a COORD to hold the buffer size and change the internal buffer size ^{\star \prime}
  bufferSize.X = 800;
   bufferSize.Y = 800;
   SetConsoleScreenBufferSize(hWnd, bufferSize);
   /* Move and resize the window */
  MoveWindow(hWnd, 5, 5, 800, 600, TRUE);
   /* Change the window title */
   SetConsoleTitle("API8810A USB Connection");
   bRetry = TRUE;
   while (bRetry)
      ^{\prime \star} Initialize the array of Cypress USB Endpoints to -1 ^{\star \prime}
      for (i = 0; i < MAX API; i++)
        aUSB 8810A Endpoints[i] = -1;
      /* Scan for USB Devices */
      nStatus = API8810A GetAPI8810AUSBDeviceCnt(&nUSBDeviceCnt);
      if (nStatus != API SUCCESS)
        printf("\nAPI8810A GetAPI8810AUSBDeviceCnt Error: %d", nStatus);
        return -1;
```

```
printf("\nDetected %d Cypress USB Devices:", nUSBDeviceCnt);
if (nUSBDeviceCnt > 0)
   /* Determine which USB devices are connected to 8810A */
   n8810ADeviceCnt = 0;
   for (i = 0; i < nUSBDeviceCnt; i++)
      nStatus = API8810A GetAPI8810ADeviceIDN(i, &sz8810AIDN[0]);
      if (nStatus != API SUCCESS)
         /* The USB device connected is not a 8810A */
         printf("\nUSB Endpoint: %d NOT 8810A device", i);
      else
         /* Replace the \r\n with a terminator character (\0) */
         for (j = 0; j < (int) strlen(sz8810AIDN); j++)
            if (sz8810AIDN[j] == '\r')
               sz8810AIDN[j] = '\0';
            }
         ^{\prime \star} Track the endpoints that are connected to 8810A ^{\star}/
         aUSB 8810A Endpoints[i] = i;
         n8810ADeviceCnt++;
         /* Display the IDN information */
         printf("\nUSB Endpoint: %d IDN:%s", i, sz8810AIDN);
   /* Request 8810A USB device to connect to */
   bValidEntry = FALSE;
   while(!bValidEntry)
      printf("\n\nPlease Enter USB Endpoint Device for 8810A to Connect: ");
      scanf("%d", &nConnectEndpoint);
      if (nConnectEndpoint < MAX API)
         if (aUSB 8810A Endpoints[nConnectEndpoint] == -1)
            printf("Endpoint entered is connected to 8810A.\n");
         else
            bValidEntry = TRUE;
      else
         printf("Endpoint entered is not valid");
   }
   /* Connect to 8810A */
   nStatus = API8810A ConnectViaUSB(1, nConnectEndpoint);
   if (nStatus != API SUCCESS)
      printf("\nAPI8810A ConnectViaUSB Error: %d", nStatus);
      return -1;
   /* Get Channel 1 Mode Information */
   nStatus = API8810A_GetAPISignalMode(1, 1, &nSigMode);
   if (nStatus != API SUCCESS)
      printf("\nAPI8810A GetAPISignalMode Error: %d", nStatus);
      return -1;
   }
   /* Display Channel 1 Mode Information */
   if (nSigMode == RESOLVER)
```

```
printf("\nChannel 1 Signal Mode = RESOLVER");
      else if (nSigMode == SYNCHRO)
         printf("\nChannel 1 Signal Mode = SYNCHRO");
      else
         printf("\nChannel 1 Signal Mode = UNKNOWN");
      /\star Disconnect from Cypress USB Devices \star/
      nStatus = API8810A DisconnectUSB(1);
      if (nStatus != API_SUCCESS)
         printf("\nAPI8810A DisconnectUSB Error: %d", nStatus);
      bRetry = FALSE;
   }
   else
      /* Request retry to find USB devices */
      bValidEntry = FALSE;
      while(!bValidEntry)
         printf("\nPlease type 'y' or 'Y' to retry USB detection: ");
         memset( buff,0x00,sizeof(buff));
         scanf("%s",buff);
         if ((buff[0] == 'y') || (buff[0] == 'Y'))
            bRetry = TRUE;
         else
            bRetry = FALSE;
         bValidEntry = TRUE;
   }
}
/* User must hit a 'q' or 'Q' to exit program */
bValidEntry = FALSE;
while(!bValidEntry)
   printf("\n\nPlease type q or Q to quit: ");
  memset( buff,0x00,sizeof(buff));
   scanf("%s",buff);
if ((buff[0] == 'q') || (buff[0] == 'Q'))
      bValidEntry = TRUE;
}
return 1;
```

Output:

```
Detected 3 Cypress USB Devices:
USB Endpoint: 0 NOT 8810A device
USB Endpoint: 1 IDN: NORTH ATLANTIC,8810AH-R,31164,5.13.4.5.4
USB Endpoint: 2 IDN: NORTH ATLANTIC,8810A-R,35524,5.18.102.102.15
Please Enter USB Endpoint Device to Connect: 1
Channel 1 Signal Mode = SYNCHRO
Please type q or Q to quit:
```

2.3 API8810A ConnectViaEthernet

Format:

```
_API8810AFUNC int API8810A_ConnectViaEthernet (
   int apiNo,
   char *szIPAddr,
   int nPort
)
```

Function Description:

This function sets up and opens the connection to communicate to the 8810A via Ethernet.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) szIPAddr - IP Address to be used to connect to 8810A. nPort - Port to be used to connect to 8810A.
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_WRITE - unable to perform ethernet login to 8810A
API_ERROR_ETHER_CONNECTION- Ethernet connection error
```

References for this function:

None.

2.4 API8810A_DisconnectIEEE

Format:

```
_API8810AFUNC int API8810A_DisconnectIEEE (
    int apiNo
)
```

Function Description:

This function closes the connection to communicate to the 8810A via IEEE.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
```

Return Value:

```
API_SUCCESS - function is successful API ERROR APINO - invalid apiNo parameter
```

References for this function:

Prior to calling this function, make call to the API8810A_ConnectViaIEEE() routine to connected to 8810A via IEEE.

2.5 API8810A_DisconnectUSB

Format:

```
API8810AFUNC int API8810A DisconnectUSB
  int apiNo
```

Function Description:

This function closes the connection to communicate to the 8810A via USB.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
```

References for this function:

Prior to calling this function, make call to the API8810A ConnectViaUSB() routine to connected to 8810A via USB.

2.6 API8810A DisconnectEthernet

Format:

```
API8810AFUNC int API8810A DisconnectEthernet
  int apiNo
```

Function Description:

This function closes the connection to communicate to the 8810A via Ethernet.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
```

References for this function:

```
Prior to calling this function, make call to the
API8810A ConnectViaEthernet() routine to connected to 8810A via Ethernet.
```

2.7 API8810A GetAPI8810AUSBDeviceCnt

```
API8810AFUNC int API8810A GetAPI8810AUSBDeviceCnt
   int *pnUSBDeviceCnt
)
```

Function Description:

This function invokes the Cypress driver and returns the number of Cypress USB Devices detected with your computer system.

Parameters:

pnUSBDeviceCnt - pointer to location to return the number of Cypress USB Devices detected

Return Value:

```
API SUCCESS - function is successful
```

References for this function:

None.

2.8 API8810A_GetAPI8810ADeviceIDN

Format:

```
_API8810AFUNC int API8810A_ GetAPI8810ADeviceIDN
  int nDeviceNo,
  char *pszIDN
```

Function Description:

This function opens the USB device specified by the device number and performs an IDN query (*IDN?\r\n) to retrieval information about the device. If the device responds with "NORTH ATLANTIC, 8810A" or its associated model, this function will populate the IDN string with the information retrieved from the device.

Parameters:

```
nDeviceNo - USB device number to open and communication via USB with
pszIDN - pointer to location to return the IDN query response
```

Return Value:

```
API SUCCESS - function is successful
API ERROR RANGE GET - value retrieved is out-of-range
API ERROR DATA - data returned from 8810A is not valid for command sent
API ERROR USB CONNECTION - USB connection error when opening device with
   Device number specified.
```

References for this function:

None

3 API-8810A Channel Routines

The routines in this section handle retrieving channel information from the 8810A device and setting channel configurations.

3.1 API8810A SetAPITrackHold

Format:

```
API8810AFUNC int API8810A SetAPITrackHold
  int apiNo,
  int nChanNo,
  bool bHold
```

Function Description:

This function sends the command to set 8810A channel specified to track or hold the angle data. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
bHold - command to track or hold channel angle
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function not supported (Track or Hold not
   supported in MATE/CIIL)
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.2 API8810A_GetAPITrackHold

Format:

```
API8810AFUNC int API8810A GetAPITrackHold
  int apiNo,
  int nChanNo,
  bool *pbHold
```

Function Description:

This function sends the command to get the track or hold state for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
```

```
nChanNo - 8810A Channel pbHold - pointer to location to return the track or hold state for the channel
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function not supported (Track or Hold not supported in MATE/CIIL)

API_ERROR_WRITE - unable to send command to 8810A

API_ERROR_RANGE_GET - value retrieved is out-of-range

API_ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.3 API8810A_SetAPISignalMode

Format:

```
_API8810AFUNC int API8810A_SetAPISignalMode (
    int apiNo,
    int nChanNo,
    int nSigMode
)
```

Function Description:

This function sends the command to set 8810A channel specified to resolver or synchro mode. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel nSigMode - signal mode to set channel Mode Types:

RESOLVER 0
SYNCHRO 1
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_RANGE_SET - parameter specified is out-of-range
API_ERROR_WRITE - unable to send command to 8810A
```

References for this function:

None.

3.4 API8810A_GetAPISignalMode

```
API8810AFUNC int API8810A GetAPISignalMode
```

```
int apiNo,
int nChanNo,
int *pnSigMode
)
```

Function Description:

This function sends the command to get the signal mode for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel pnSigMode - pointer to location to return the channel signal mode Mode Types:

RESOLVER 0
SYNCHRO 1
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_WRITE - unable to send command to 8810A
API_ERROR_RANGE_GET - value retrieved is out-of-range
API_ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.5 API8810A_SetAPIReferenceSrc

Format:

```
_API8810AFUNC int API8810A_SetAPIReferenceSrc (
   int apiNo,
   int nChanNo,
   int nRefSrc )
```

Function Description:

This function sends the command to set 8810A channel specified to internal or external reference mode. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

Return Value:

```
API SUCCESS - function is successful
```

```
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR RANGE SET - parameter specified is out-of-range
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.6 API8810A_GetAPIReferenceSrc

Format:

```
API8810AFUNC int API8810A GetAPIReferenceSrc
  int apiNo,
  int nChanNo,
  int *pnRefSrc
```

Function Description:

This function sends the command to get the reference mode for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
pnRefSrc - pointer to location to return the reference mode
                 Reference Source Types:
                    INTERNAL
                                      Ω
                                      1
                    EXTERNAL
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR RANGE GET - value retrieved is out-of-range
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.7 API8810A SetAPIRatio

Format:

```
API8810AFUNC int API8810A SetAPIRatio
  int apiNo,
  int nChanNo,
  int nRatio
```

Function Description:

This function sends the command to set the ratio value for the specified 8810A channel. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel nRatio - ratio value set channel (1 - 255)
```

Return Value:

References for this function:

None.

3.8 API8810A_GetAPIRatio

Format:

```
_API8810AFUNC int API8810A_GetAPIRatio (
   int apiNo,
   int nChanNo,
   int *pnRatio
)
```

Function Description:

This function sends the command to get the ratio value for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel pnRatio - pointer to location to return the ratio value
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.9 API8810A SetAPIAutoBandwidth

Format:

```
_API8810AFUNC int API8810A_SetAPIAutoBandwidth (
   int apiNo,
   int nChanNo
)
```

Function Description:

This function sends the command to set the bandwidth to "auto" mode for the specified 8810A channel. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX\_API) nChanNo - 8810A Channel
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_FUNC_NOT_SUPPORTED - function supported only with
API8810A_NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.10 API8810A_SetAPIBandwidth

Format:

```
_API8810AFUNC int API8810A_SetAPIBandwidth (
   int apiNo,
   int nChanNo,
   int nBandwidth
```

Function Description:

This function sends the command to set the bandwidth to "override" mode with the bandwidth specified for the specified 8810A channel. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel nBandwidth - Bandwidth to set the channel
```

Return Value:

```
API_SUCCESS - function is successful API ERROR APINO - invalid apiNo parameter
```

```
API_ERROR_FUNC_NOT_SUPPORTED - function supported only with API8810A_NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.11 API8810A_GetAPIBandwidth

Format:

```
_API8810AFUNC int API8810A_GetAPIBandwidth (
   int apiNo,
   int nChanNo,
   bool *pbAutoBW,
   int *pnBandwidth
```

Function Description:

This function sends the command to get the bandwidth mode and bandwidth value for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel pbAutoBW - pointer to location to return the bandwidth mode indicator pnBandwidth - pointer to location to return the bandwidth value
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.12 API8810A_GetAPIAngle

Format:

```
_API8810AFUNC int API8810A_GetAPIAngle (
   int apiNo,
   int nChanNo,
   double *pdAngle
)
```

Function Description:

This function sends the command or perform an IEEE read (with 8810 Legacy languages) to get angle value for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
pdAngle - pointer to location to return the angle value
```

Return Value:

```
API SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.13 API8810A_GetAPIAvgAngle

Format:

```
API8810AFUNC int API8810A GetAPIAvgAngle
  int apiNo,
  int nChanNo,
  double *pdAvgAngle
```

Function Description:

This function sends the command or perform an IEEE read (with 8810 Legacy languages) to get angle value for the 8810A channel. In API8810A NATIVE language mode, if the angle averaging is turned on, the average angle value is returned by the unit, otherwise the angle value is returned by the unit.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
pdAvgAngle - pointer to location to return the angle average value
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None

3.14 API8810A GetAPIVelocity

```
API8810AFUNC int API8810A GetAPIVelocity
  int apiNo,
  int nChanNo,
```

```
double *pdVelocity
```

Function Description:

This function sends the command to get angle velocity value for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX\_API) nChanNo - 8810A Channel pdVelocity - pointer to location to return the angle velocity value
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.15 API8810A_GetAPILineLineVolt

Format:

```
_API8810AFUNC int API8810A_GetAPILineLineVolt (
   int apiNo,
   int nChanNo,
   double *pdLineLineVolt
)
```

Function Description:

This function sends the command to get line-to-line voltage value for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
pdLineLineVolt - pointer to location to return the line-to-line voltage
   value
```

Return Value:

References for this function:

None.

3.16 API8810A GetAPINullVolt

Format:

```
_API8810AFUNC int API8810A_GetAPINullVolt (
   int apiNo,
   int nChanNo,
   double *pdNullVolt
)
```

Function Description:

This function sends the command to get null voltage value for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel pdNullVolt - pointer to location to return the null voltage value
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

Remarks:

Currently the 8810A device will always return 0 for the null voltage.

3.17 API8810A GetAPIRefVolt

Format:

```
_API8810AFUNC int API8810A_GetAPIRefVolt (
   int apiNo,
   int nChanNo,
   double *pdRefVolt
)
```

Function Description:

This function sends the command to get reference voltage value for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel pdRefVolt - pointer to location to return the reference voltage value
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.18 API8810A_GetAPIRefFreq

Format:

```
API8810AFUNC int API8810A GetAPIRefFreq
  int apiNo,
  int nChanNo,
  double *pdRefFreq
```

Function Description:

This function sends the command to get reference frequency value for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
pdRefFreq - pointer to location to return the reference frequency value
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.19 API8810A_SetAPIAvgState

Format:

```
API8810AFUNC int API8810A SetAPIAvgState
  int apiNo,
  int nChanNo,
  bool bAvgStateOn
```

Function Description:

This function sends the command to turn on or off the angle averaging mode for the specified 8810A channel. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
bAvgStateOn - Turn on or off angle averaging for the channel
```

Return Value:

References for this function:

None.

3.20 API8810A_GetAPIAvgState

Format:

```
_API8810AFUNC int API8810A_GetAPIAvgState (
   int apiNo,
   int nChanNo,
   bool *pbAvgStateOn
)
```

Function Description:

This function sends the command to get the angle averaging mode for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel pbAvgStateOn - pointer to location to return the angle averaging mode
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.21 API8810A SetAPIAvgRate

```
\_API8810AFUNC int API8810A\_SetAPIAvgRate (
```

```
int apiNo,
int nChanNo,
int nAvgRate
```

Function Description:

This function sends the command to set the angle averaging rate in msec for the specified 8810A channel. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel nAvgRate - angle averaging rate to set for the channel (10-10000 msec)
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_RANGE_SET - parameter specified is out-of-range

API_ERROR_WRITE - unable to send command to 8810A
```

References for this function:

None.

3.22 API8810A_GetAPIAvgRate

Format:

```
_API8810AFUNC int API8810A_GetAPIAvgRate (
   int apiNo,
   int nChanNo,
   int *pnAvgRate
```

Function Description:

This function sends the command to get the angle averaging rate for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChanNo - 8810A Channel pnAvgRate - pointer to location to return the angle averaging rate
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.23 API8810A SetAPIAngLimitState

Format:

```
API8810AFUNC int API8810A SetAPIAngLimitState
  int apiNo,
  int nChanNo,
  bool bAngLmtOn
```

Function Description:

This function sends the command to turn on or off the angle limit testing mode for the specified 8810A channel. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
bAngLmtOn - Turn on or off angle limit testing for the channel
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.24 API8810A_GetAPIAngLimitState

Format:

```
API8810AFUNC int API8810A GetAPIAngLimitState
  int apiNo,
  int nChanNo,
  bool *pbAngLmtOn
```

Function Description:

This function sends the command to get the angle limit testing mode for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
pbAngLmtOn - pointer to location to return the angle limit testing mode
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API_ERROR_WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.25 API8810A SetAPIAngLimitCompare

Format:

```
API8810AFUNC int API8810A SetAPIAngLimitCompare
  int apiNo,
  int nChanNo,
  int nAngLimitCompare
```

Function Description:

This function sends the command to set 8810A channel specified with the angle comparison mode for angle limit testing. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
nAngLimitCompare - comparison mode for angle limit testing to set channel
                  Angle Limit Comparison Mode Types:
                     ANGLE LIMIT ABS ANG
                     ANGLE LIMIT ANG ERR
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR RANGE - parameter specified is out-of-range
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.26 API8810A_GetAPIAngLimitCompare

```
API8810AFUNC int API8810A GetAPIAngLimitCompare
  int apiNo,
```

```
int nChanNo,
   char *pszAngLimitCompare
```

Function Description:

This function sends the command to get the angle comparison mode for angle limit testing for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
pszAngLimitCompare - pointer to location to return the angle comparison
mode for angle limit testing
```

Return Value:

References for this function:

None.

3.27 API8810A_SetAPIAngUpperLimit

Format:

```
_API8810AFUNC int API8810A_SetAPIAngUpperLimit (
   int apiNo,
   int nChanNo,
   double dAngUpperLimit
)
```

Function Description:

This function sends the command to set 8810A channel specified with the upper angle limit value for angle limit testing. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
dAngUpperLimit - upper angle limit value to set channel for angle limit
testing (0-360.0)
```

Return Value:

```
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.28 API8810A_GetAPIAngUpperLimit

Format:

```
API8810AFUNC int API8810A GetAPIAngUpperLimit
  int apiNo,
  int nChanNo,
  double *pdAngUpperLimit
```

Function Description:

This function sends the command to get the upper angle limit value for angle limit testing for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
pdAngUpperLimit - pointer to location to return the upper angle limit
   value for angle limit testing
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API_ERROR_WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.29 API8810A_SetAPIAngLowerLimit

Format:

```
API8810AFUNC int API8810A SetAPIAngLowerLimit
  int apiNo,
  int nChanNo,
  double dAngLowerLimit
```

Function Description:

This function sends the command to set 8810A channel specified with the lower angle limit value for angle limit testing. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
dAngLowerLimit - lower angle limit value to set channel for angle limit
   testing (0-360.0)
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR RANGE SET - parameter specified is out-of-range
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.30 API8810A_GetAPIAngLowerLimit

Format:

```
API8810AFUNC int API8810A GetAPIAngLowerLimit
  int apiNo,
  int nChanNo,
  double *pdAngLowerLimit
```

Function Description:

This function sends the command to get the lower angle limit value for angle limit testing for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
pdAngLowerLimit - pointer to location to return the lower angle limit
   value for angle limit testing
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.31 API8810A SetAPIAngLimitErrorStep

```
API8810AFUNC int API8810A SetAPIAngLimitErrorStep
  int apiNo,
```

```
int nChanNo,
double dAngLimitErrorStep
```

Function Description:

This function sends the command to set 8810A channel specified with the angle step value for angle error comparison for angle limit testing. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
dAngLimitErrorStep - angle step value to set channel for angle limit
  testing (0-360.0)
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR RANGE SET - parameter specified is out-of-range
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.32 API8810A_GetAPIAngLimitErrorStep

Format:

```
API8810AFUNC int API8810A GetAPIAngLimitErrorStep
  int apiNo,
  int nChanNo,
  double *pdAngLimitErrorStep
```

Function Description:

This function sends the command to get the angle step value for angle error comparison for angle limit testing for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
pdAngLimitErrorStep - pointer to location to return the angle step value
   for angle error comparison for angle limit testing.
```

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API_ERROR_WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

None.

3.33 API8810A_SetAPIDAOutput

Format:

```
_API8810AFUNC int API8810A_SetAPIDAOutput (
    int apiNo,
    int nChanNo,
    int nDAOutput
```

Function Description:

This function sends the command to set 8810A channel specified with the data type to use for DA output. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
nDAOutput - data type mode for DA output
DA Output Data Types:
DA_ANGLE_OUTPUT
DA VELOCITY OUTPUT
1
```

Return Value:

References for this function:

None.

3.34 API8810A_GetAPIDAOutput

Format:

```
_API8810AFUNC int API8810A_GetAPIDAOutput (
   int apiNo,
   int nChanNo,
   char *pszDAOutput
)
```

Function Description:

This function sends the command to get the data type to use for DA output for the 8810A channel.

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
pszDAOutput - pointer to location to return the data type for DA output
```

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.35 API8810A_SetAPIDAUpperLimit

Format:

```
API8810AFUNC int API8810A SetAPIDAUpperLimit
  int apiNo,
  int nChanNo,
  double dDAUpperLimit
```

Function Description:

This function sends the command to set 8810A channel specified with the upper angle or velocity limit value for DA output. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChanNo - 8810A Channel
dDAUpperLimit - upper angle or velocity limit value to set channel for DA
  Output
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.36 API8810A GetAPIDAUpperLimit

Format:

```
API8810AFUNC int API8810A GetAPIDAUpperLimit
  int apiNo,
```

```
int nChanNo,
  double *pdDAUpperLimit
)
```

Function Description:

This function sends the command to get the upper angle or velocity limit value for DA output for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
pdDAUpperLimit - pointer to location to return the upper angle or velocity
   limit for DA output.
```

Return Value:

References for this function:

None.

3.37 API8810A_SetAPIDALowerLimit

Format:

```
_API8810AFUNC int API8810A_SetAPIDALowerLimit (
   int apiNo,
   int nChanNo,
   double dDALowerLimit
```

Function Description:

This function sends the command to set 8810A channel specified with the lower angle or velocity limit value for DA output. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
dDALowerLimit - lower angle or velocity limit value to set channel for DA
   Output
```

Return Value:

www.naii.com / e-mail:sales@naii.com

None.

3.38 API8810A GetAPIDALowerLimit

Format:

```
_API8810AFUNC int API8810A_GetAPIDALowerLimit (
   int apiNo,
   int nChanNo,
   double *pdDALowerLimit)
```

Function Description:

This function sends the command to get the lower angle or velocity limit value for DA output for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
pdDALowerLimit - pointer to location to return the lower angle or velocity
    limit for DA output.
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API_ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.39 API8810A_SetAPIDAUpperVoltage

Format:

```
_API8810AFUNC int API8810A_SetAPIDAUpperVoltage (
   int apiNo,
   int nChanNo,
   double dDAUpperVoltage
)
```

Function Description:

This function sends the command to set 8810A channel specified with the voltage value associated with the upper limit for DA output. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
```

```
nChanNo - 8810A Channel dDAUpperVoltage - voltage value associated with upper limit value to set channel for DA Output
```

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_FUNC_NOT_SUPPORTED - function supported only with
API8810A_NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.40 API8810A_GetAPIDAUpperVoltage

Format:

```
_API8810AFUNC int API8810A_GetAPIDAUpperVoltage (
   int apiNo,
   int nChanNo,
   double *pdDAUpperVoltage
)
```

Function Description:

This function sends the command to get the voltage value associated with the upper limit value for DA output for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
pdDAUpperVoltage - pointer to location to return the voltage value
   associated with upper limit value for DA output.
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.41 API8810A_SetAPIDALowerVoltage

Format:

```
_API8810AFUNC int API8810A_SetAPIDALowerVoltage (
   int apiNo,
   int nChanNo,
   double dDALowerVoltage
```

)

Function Description:

This function sends the command to set 8810A channel specified with the voltage value associated with the lower limit for DA output. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
dDALowerVoltage - voltage value associated with lower limit value to set
    channel for DA Output
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_FUNC_NOT_SUPPORTED - function supported only with
API8810A_NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

3.42 API8810A_GetAPIDALowerVoltage

Format:

```
_API8810AFUNC int API8810A_GetAPIDALowerVoltage (
   int apiNo,
   int nChanNo,
   double *pdDALowerVoltage
```

Function Description:

This function sends the command to get the voltage value associated with the lower limit value for DA output for the 8810A channel.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nChanNo - 8810A Channel
pdDALowerVoltage - pointer to location to return the voltage value
   associated with lower limit value for DA output.
```

Return Value:

References for this function:

None.

3.43 API8810A_SetAPIDisplayAngDiffState

Format:

```
_API8810AFUNC int API8810A_SetAPIDisplayAngDiffState (
   int apiNo,
   int nAngDiffState
)
```

Function Description:

This function sends the command to turn on or off the angle difference mode. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

Remarks:

When the 8810A device received the command to turn on the angle difference mode, it will automatically revert to the Dual Channel screen so that the angle difference data is visible on the 8810A display.

3.44 API8810A_GetAPIDisplayAngDiffState

Format:

```
_API8810AFUNC int API8810A_GetAPIDisplayAngDiffState (
   int apiNo,
   int *pnAngDiffState
)
```

Function Description:

This function sends the command to get the angle difference mode setting.

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX\_API) Function Reference North Atlantic Industries, Inc. 631.567.1100 Revision 3.0.0.2 Manual for 8810A 110 Wilbur Place, Bohemia, NY 11716 www.naii.com / e-mail:sales@naii.com
```

```
pnAngDiffState - pointer to location to return the angle difference mode
                  Angle Difference Mode Types:
                     ANG_DIFF_DISABLED
                     ANG DIFF ENABLED
                                             1
```

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

3.45 API8810A_GetAPIAngleDiff

Format:

```
API8810AFUNC int API8810A GetAPIAngleDiff
  int apiNo,
  double *pdAngleDiff
```

Function Description:

This function sends the command to get difference between angle value for the Channel 1 and Channel 2 signal.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX API) pdAngleDiff - pointer to location to return the angle difference value

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

4 API-8810A Multiple Channel Query Routines

The routines in this section handle retrieving channel information from the 8810A device using one query call rather than individual query calls for each channel.

API8810A_GetAPIAngles

Format:

```
API8810AFUNC int API8810A GetAPIAngles
  int apiNo,
  double *pdAngle1,
  double *pdAngle2
```

Function Description:

This function sends the command to get the angle values for both 8810A channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pdAngle1- pointer to location to return the angle value for Channel 1
pdAngle2- pointer to location to return the angle value for Channel 2
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

API8810A GetAPIAvgStates

Format:

```
API8810AFUNC int API8810A GetAPIAvgStates
  int apiNo,
 bool *pbAvgStateOn1,
  int *pnAvgRate1,
  bool *pbAvgStateOn2,
  int *pnAvgRate2
```

Function Description:

This function sends the command to get the angle averaging mode and the average rates for both 8810A channels.

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
pbAvgStateOn1 - pointer to location to return the angle averaging mode for
   Channel 1
pnAvgRate1- pointer to location to return the average rate value for
   Channel 1
pbAvgStateOn2 - pointer to location to return the angle averaging mode for
   Channel 2
pnAvgRate2- pointer to location to return the average rate value for
   Channel 2
```

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API_ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

4.3 API8810A_GetAPIAvgAngles

Format:

```
_API8810AFUNC int API8810A_GetAPIAvgAngles (
   int apiNo,
   double *pdAvgAngle1,
   double *pdAvgAngle2
)
```

Function Description:

This function sends the command to get the angle average values for both 8810A channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
pdAvgAngle1- pointer to location to return the angle average value for
   Channel 1
pdAvgAngle2- pointer to location to return the angle average value for
   Channel 2
```

Return Value:

References for this function:

4.4 API8810A GetAPIBandwidths

Format:

```
_API8810AFUNC int API8810A_GetAPIBandwidths (
   int apiNo,
   bool *pbAutoBW1,
   int *pnBandwidth1,
   bool *pbAutoBW2,
   int *pnBandwidth2
)
```

Function Description:

This function sends the command to get the bandwidth modes and bandwidth values for both 8810A channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
pbAutoBW1 - pointer to location to return the bandwidth mode for Channel 1
pnBandwidth1- pointer to location to return the bandwidth value for
    Channel 1
pbAutoBW2 - pointer to location to return the bandwidth mode for Channel 2
pnBandwidth2- pointer to location to return the bandwidth value for
    Channel 2
```

Return Value:

References for this function:

None.

4.5 API8810A_GetAPISignalModes

Format:

```
_API8810AFUNC int API8810A_GetAPISignalModes (
   int apiNo,
   int *pnSigMode1,
   int *pnSigMode2
```

Function Description:

This function sends the command to get signal modes for both 8810A channels.

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) pnSigModel- pointer to location to return the signal mode for Channel 1
```

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

4.6 API8810A_GetAPIRatios

Format:

```
_API8810AFUNC int API8810A_GetAPIRatios (
   int apiNo,
   int *pnRatio1,
   int *pnRatio2
)
```

Function Description:

This function sends the command to get ratio values for both $8810\mbox{A}$ channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) pnRatio1- pointer to location to return the ratio value for Channel 1 pnRatio2- pointer to location to return the ratio value for Channel 2
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API_ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

4.7 API8810A_GetAPIReferenceSrcs

Format:

```
_API8810AFUNC int API8810A_GetAPIReferenceSrcs (
   int apiNo,
   int *pnRefSrc1,
```

```
int *pnRefSrc2
```

Function Description:

This function sends the command to get reference modes for both 8810A

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pnRefSrc1- pointer to location to return the reference mode for Channel 1
pnRefSrc2- pointer to location to return the reference mode for Channel 2
                  Reference Source Types:
                     INTERNAL
                     EXTERNAL
                                       1
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

API8810A_GetAPITrackHolds

Format:

```
API8810AFUNC int API8810A GetAPITrackHolds
  int apiNo,
  bool *pbHold1,
  bool *pbHold2
```

Function Description:

This function sends the command to get track or hold states for both 8810A channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pbHold1- pointer to location to return the track or hold state for Channel 1
pbHold2- pointer to location to return the track or hold state for Channel 2
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

API8810A_GetAPIAngLimitStates

Format:

```
API8810AFUNC int API8810A GetAPIAngLimitStates
  int apiNo,
  bool *pbAngLmtOn1,
  int *pnAngLimitCmp1,
  bool *pbAnqLmtOn2,
  int *pnAngLimitCmp2
```

Function Description:

This function sends the command to get angle limit testing states and comparison modes for both 8810A channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pbAngLmtOn1- pointer to location to return the angle limit testing state
   for Channel 1
pnAngLimitCmp1 - pointer to location to return the angle comparison mode
   for Channel 1
pbAngLmtOn2- pointer to location to return the angle limit testing state
   for Channel 2
pnAngLimitCmp2 - pointer to location to return the angle comparison mode
   for Channel 2
                  Angle Limit Comparison Mode Types:
                     ANGLE LIMIT ABS ANG
                     ANGLE LIMIT ANG ERR
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

4.10 API8810A GetAPIVelocities

Format:

```
API8810AFUNC int API8810A GetAPIVelocities
  int apiNo,
  double *pdVelocity1,
  double *pdVelocity2
```

Function Description:

This function sends the command to get the angle velocity values for both 8810A channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) pdVelocity1- pointer to location to return the velocity value for Channel 1 pdVelocity2- pointer to location to return the velocity value for Channel 2
```

Return Value:

References for this function:

None.

4.11 API8810A GetAPILineLineVolts

Format:

```
_API8810AFUNC int API8810A_GetAPILineLineVolts (
   int apiNo,
   double *pdLineLineVolt1,
   double *pdLineLineVolt2
)
```

Function Description:

This function sends the command to get the line-to-line voltage values for both 8810A channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
pdLineLineVolt1- pointer to location to return the line-to-line voltage
  value for Channel 1
pdLineLineVolt2- pointer to location to return the line-to-line voltage
  value for Channel 2
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

4.12 API8810A_GetAPINullVolts

Format:

```
API8810AFUNC int API8810A GetAPINullVolts
  int apiNo,
  double *pdNullVolt1,
  double *pdNullVolt2
```

Function Description:

This function sends the command to get the null voltage values for both 8810A channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pdNullVolt1- pointer to location to return the null voltage value for
   Channel 1
pdNullVolt2- pointer to location to return the null voltage value for
   Channel 2
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

4.13 API8810A GetAPIRefVolts

Format:

```
API8810AFUNC int API8810A GetAPIRefVolts
  int apiNo,
  double *pdRefVolt1,
  double *pdRefVolt2
```

Function Description:

This function sends the command to get the reference voltage values for both 8810A channels.

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pdRefVolt1- pointer to location to return the reference voltage value for
pdRefVolt2- pointer to location to return the reference voltage value for
   Channel 2
```

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API_ERROR_WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

4.14 API8810A_GetAPIRefFreqs

Format:

```
API8810AFUNC int API8810A GetAPIRefFreqs
  int apiNo,
  double *pdRefFreq1,
  double *pdRefFreq2
```

Function Description:

This function sends the command to get the reference frequency values for both 8810A channels.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pdRefFreq1- pointer to location to return the reference frequency value
   for Channel 1
pdRefFreq2- pointer to location to return the reference frequency value
   for Channel 2
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

5 API-8810A Internal Reference Routines

The routines in this section handle retrieving and setting configurations for the reference module in the 8810A device if available.

5.1 API8810A_SetIntRefFreq

Format:

```
_API8810AFUNC int API8810A_SetIntRefFreq (
   int apiNo,
   double dFreq )
```

Function Description:

This function sends the command to set the reference frequency for the reference module (if available). Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) dFreq - Frequency value to set the reference module
```

Return Value:

References for this function:

None.

5.2 API8810A_GetIntRefFreq

Format:

```
_API8810AFUNC int API8810A_GetIntRefFreq (
    int apiNo,
    double *pdFreq )
```

Function Description:

This function sends the command to get the reference frequency for the reference module.

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
pdFreq - pointer to location to return the frequency value to set the
   reference module
```

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API_ERROR_WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

Remarks:

If the 8810A unit does not contain a reference module, the device will always return 400 Hz for the frequency value.

5.3 API8810A SetIntRefVolt

Format:

```
API8810AFUNC int API8810A SetIntRefVolt
  int apiNo,
  double dVolt
```

Function Description:

This function sends the command to set the reference voltage for the reference module (if available). Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
dVolt - Voltage value to set the reference module
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

5.4 API8810A GetIntRefVolt

Format:

```
API8810AFUNC int API8810A GetIntRefVolt
   int apiNo,
   double *pdVolt
)
```

Function Description:

This function sends the command to get the reference voltage for the reference module.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
pdVolt - pointer to location to return the voltage value to set the
 reference module

Return Value:

References for this function:

None.

Remarks:

If the 8810A unit does not contain a reference module, the device will always return 26 volts for the voltage value.

5.5 API8810A_SetIntRefOutputState

Format:

```
_API8810AFUNC int API8810A_SetIntRefOutputState (
   int apiNo,
   int nOutputState
)
```

Function Description:

This function sends the command to set the reference output state for the reference module (if available). Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nOutputState - Output state value to set the reference module
Reference Output States:
INT_REF_OUT_NOT_AVAILABLE 0
INT_REF_OUT_AVAILABLE 1
```

None.

5.6 API8810A_GetIntRefOutputState

Format:

```
API8810AFUNC int API8810A GetIntRefOutputState
  int apiNo,
  int *pnOutputState
```

Function Description:

This function sends the command to get the reference output state for the reference module.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pnOutputState - pointer to location to return the reference output state
   to set the reference module
                  Reference Output States:
                     INT REF OUT NOT AVAILABLE
                     INT REF OUT AVAILABLE
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API_ERROR_WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

Remarks:

```
If the 8810A unit does not contain a reference module, the device will
always return INT REF OUT NOT AVAILABLE.
```

5.7 API8810A GetIntRefOverCurrentState

Format:

```
API8810AFUNC int API8810A GetIntRefOverCurrentState
  int apiNo,
  bool *pbIntRefOverCurrent
```

Function Description:

This function sends the command to get the reference over-current state for the reference module.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pbIntRefOverCurrent - pointer to location to return the reference over-
current state to set the reference module
                  Reference Over-current States:
                     true - Reference is in over-current state
```

false - Reference is not in over-current state

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

Remarks:

If the 8810A unit does not contain a reference module, the device will always return false.

5.8 API8810A_ResetIntRefOverCurrent

Format:

```
API8810AFUNC int API8810A ResetIntRefOverCurrent
  int apiNo
```

Function Description:

This function sends the command to reset the reference over-current state for the reference module (if available).

Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX API)

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

6 API-8810A Command Routines

The routines in this section handle sending commands such as retrieval of the device ID and errors on the error queue, and resetting the 8810A device setting to factory default settings.

6.1 API8810A_PerformGetID

Format:

```
_API8810AFUNC int API8810A_PerformGetID (
   int apiNo,
   char *pszID )
```

Function Description:

This function sends the IDN command to get Device ID string for the device. The ID returned includes the manufacturer (NORTH ATLANTIC), the 8810A module, serial number, and revision information.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) pszID - pointer to location to return the device ID
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_WRITE - unable to send command to 8810A
API_ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

6.2 API8810A Reset

Format:

```
_API8810AFUNC int API8810A_Reset (
   int apiNo,
   char *pszResults
)
```

Function Description:

This function sends the command to reset the 8810A device and set the device setting back to the factory default settings. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

"Reset Not Performed" - reset has not been successful.

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

6.3 API8810A_GetErrors

Format:

```
API8810AFUNC int API8810A GetErrors
  int apiNo,
  char *pszErrors
```

Function Description:

This function sends the ERR command to get error from the error queue for the device. "No error" is returned when there are no errors on the queue.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pszErrors - pointer to location to return the error string
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

7 API-8810A Configuration Routines

The routines in this section handle sending commands to set and retrieve the configuration settings of the 8810A device.

7.1 API8810A_GetIEEELang

Format:

```
_API8810AFUNC int API8810A_GetIEEELang (
   int apiNo,
   char *pszIEEELang
)
```

Function Description:

This function sends the command to get the IEEE language protocol set in the 8810A.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) pszIEEELang - pointer to location to return the IEEE protocol string Return values:

"API8810A Native" - API-8810A Native

"API8810 Native" - API-8810 Native (Legacy)

"API8810 SR103" - API-8810 SR103 (Legacy)

"API8810 HSR202" - API-8810 HSR202 (Legacy)

"API8810 MATE/CIIL" - API-8810 MATE/CIIL (Legacy)

"API8810 FX2" - API-8810 FX2
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_WRITE - unable to send command to 8810A
API_ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

7.2 API8810A_SetIEEELang

Format:

```
_API8810AFUNC int API8810A_SetIEEELang (
   int apiNo,
   int nIEEELang
```

Function Description:

This function sends the command to set the IEEE protocol language to accept when communicating via IEEE. Note the 8810A device will not accept

the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nIEEELang - Language Protocol to be used to communicate via IEEE to 8810A.
```

```
8810A Language Types:

API8810A_NATIVE 0

IEEE_API8810_NATIVE 1

IEEE_API8810_SR103 2

IEEE_API8810_HSR202 3

IEEE_API8810_HSR203 4

IEEE_API8810_MATECIIL 5

IEEE_API8810_FX2 6
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

7.3 API8810A_GetCommState

Format:

```
_API8810AFUNC int API8810A_GetCommState (
   int apiNo,
   char *pszCommState
)
```

Function Description:

This function sends the command to get the communication mode set in the 8810A.

Parameters:

```
"Local Mode"

"Remote IEEE Addr: API-IEEE Language"

"Remote USB"

"Remote Ethernet"

"Remote J1"

"Remote with Lockout via IEEE Addr: API-IEEE Language"

"Remote with Lockout via USB"

"Remote with Lockout via Ethernet"

"Remote with Lockout via J1"
```

Return Value:

```
API_SUCCESS - function is successful API ERROR APINO - invalid apiNo parameter
```

www.naii.com / e-mail:sales@naii.com

```
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API_ERROR_WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

None.

7.4 API8810A_GoToLocal

Format:

```
API8810AFUNC int API8810A GoToLocal
  int apiNo
```

Function Description:

This function sends the command to set the communication mode to Local mode. In Local mode, remote "set" commands will not be accepted.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX API)

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None

7.5 API8810A SetLocalLockout

Format:

```
API8810AFUNC int API8810A SetLocalLockout
  int apiNo
```

Function Description:

This function sends the command to lockout configuration setting such as track or hold, signal mode, reference mode, and ratio setting from the 8810A front panel. Note the 8810A device will not accept the command if device is set to Local mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
```

```
API SUCCESS - function is successful
```

```
API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API ERROR WRITE - unable to send command to 8810A
```

None.

7.6 API8810A_SetRemoteUSB

Format:

```
_API8810AFUNC int API8810A_SetRemoteUSB (
    int apiNo
)
```

Function Description:

This function sends the command to set the communication mode to Remote USB mode. In Remote USB mode, remote "set" commands will be accepted if the command is received from the USB interface.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX API)

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

7.7 API8810A SetRemoteEthernet

Format:

```
_API8810AFUNC int API8810A_SetRemoteEthernet(
    int apiNo
```

Function Description:

This function sends the command to set the communication mode to Remote Ethernet mode. In Remote Ethernet mode, remote "set" commands will be accepted if the command is received from the Ethernet interface.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
```

```
API SUCCESS - function is successful
```

```
API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API ERROR WRITE - unable to send command to 8810A
```

None.

7.8 API8810A_SetRemoteIEEE

Format:

```
_API8810AFUNC int API8810A_SetRemoteIEEE (
    int apiNo )
```

Function Description:

This function sends the command to set the communication mode to Remote IEEE mode. In Remote IEEE mode, remote "set" commands will be accepted if the command is received from the IEEE interface.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX API)

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

7.9 API8810A SetRemoteJ1

Format:

```
_API8810AFUNC int API8810A_SetRemoteJ1 (
    int apiNo )
```

Function Description:

This function sends the command to set the communication mode to Remote J1 mode. In Remote J1 mode, remote "set" commands will be accepted if the command is received from the J1 interface.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
```

```
API SUCCESS - function is successful
```

```
API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API ERROR WRITE - unable to send command to 8810A
```

None.

7.10 API8810A_SetAngleDisplayFormat

Format:

```
_API8810AFUNC int API8810A_SetAngleDisplayFormat (
    int apiNo,
    int nDisplayFormat
)
```

Function Description:

This function sends the command to set the angle display format. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

Return Value:

References for this function:

None.

7.11 API8810A_GetAngleDisplayFormat

Format:

```
_API8810AFUNC int API8810A_GetAngleDisplayFormat (
   int apiNo,
   int *pnDisplayFormat
)
```

Function Description:

This function sends the command to get the angle display format set in the 8810A.

Parameters:

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API_ERROR_RANGE_GET - value retrieved is out-of-range

API_ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

7.12 API8810A_SetCh1Input

Format:

```
_API8810AFUNC int API8810A_SetChlInput (
   int apiNo,
   int nChlInputConnector
)
```

Function Description:

This function sends the command to set the Channel 1 input connector configuration. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) nChlInputConnector - Channel 1 input connector configuration on the 8810A Channel 1 Input Configuration Types:

CH1_INPUT_FRONT_CONNECTOR 0
CH1_INPUT_BACK_CONNECTOR 1
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API ERROR WRITE - unable to send command to 8810A
```

References for this function:

7.13 API8810A_GetCh1Input

Format:

```
_API8810AFUNC int API8810A_GetCh1Input (
    int apiNo,
    int *pnCh1InputConnector
)
```

Function Description:

This function sends the command to get the Channel 1 input connector configuration set in the 8810A.

Parameters:

Return Value:

References for this function:

None.

7.14 API8810A_SetTouchscreenState

Format:

```
_API8810AFUNC int API8810A_SetTouchscreenState (
   int apiNo,
   int nTouchscreenState
)
```

Function Description:

This function sends the command to set the touch screen configuration. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nTouchscreenState - Touch screen configuration on the 8810A
Touch screen Configuration Types:
TOUCHSCREEN_DISABLED 0
TOUCHSCREEN ENABLED 1
```

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

7.15 API8810A GetTouchscreenState

Format:

```
API8810AFUNC int API8810A GetTouchscreenState
  int apiNo,
  int *pnTouchscreenState
```

Function Description:

This function sends the command to get the touch screen configuration set in the 8810A.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pnTouchscreenState - pointer to location to return the touch screen
   configuration
                  Touchscreen Configuration Types:
                     TOUCHSCREEN DISABLED
                     TOUCHSCREEN ENABLED
                                              1
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

7.16 API8810A_SetDisplayState

Format:

```
API8810AFUNC int API8810A SetDisplayState
  int apiNo,
  int nDisplayState
```

Function Description:

This function sends the command to set the main display state. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nDisplayState - Display configuration on the 8810A
                  Display Configuration Types:
                     CHAN1 DISPLAY
                     CHAN2 DISPLAY
                                                 1
                     CHAN1 ANALOG DISPLAY
                     CHAN2 ANALOG DISPLAY
                     DUAL DISPLAY
                     REFERENCE DISPLAY
                                                5
                     CHARTING DISPLAY
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR RANGE- data returned from 8810A is not valid for command sent
```

References for this function:

None.

7.17 API8810A_GetDisplayState

Format:

```
API8810AFUNC int API8810A GetDisplayState
  int apiNo,
  int *pnDisplayState
```

Function Description:

This function sends the command to get the main display configuration on the 8810A.

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pnDisplayState - pointer to location to return the main screen
   configuration state.
```

```
Main Screen Configuration Types:
  CHAN1 DISPLAY
   CHAN2 DISPLAY
   CHAN1 ANALOG DISPLAY
   CHAN2_ANALOG_DISPLAY
   DUAL DISPLAY
   REFERENCE DISPLAY
  CHARTING DISPLAY
```

UNKNOWN DISPLAY

-1

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR RANGE GET - value retrieved is out-of-range
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

7.18 API8810A ResetDefaultValues

Format:

```
API8810AFUNC int API8810A ResetDefaultValues
  int apiNo
```

Function Description:

This function sends the command to set the device setting back to the factory default settings. This command will also reset the calibration values and a calibration of the device is recommended after issuing this command. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX API)

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR RANGE- data returned from 8810A is not valid for command sent
```

References for this function:

8 API-8810A Calibration Routines

The routines in this section handle sending commands to calibrate the 8810A device and retrieve the calibration state of the 8810A device.

8.1 API8810A_GetCalState

Format:

```
_API8810AFUNC int API8810A_GetCalState (
   int apiNo,
   char *pszCalState
)
```

Function Description:

This function sends the command to get the calibration state of the 8810A.

Parameters:

Return Value:

References for this function:

None.

8.2 API8810A_Calibrate

Format:

```
_API8810AFUNC int API8810A_Calibrate
(
   int apiNo
)
```

Function Description:

This function sends the command to calibrate the 8810A. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

8.3 API8810A_SetAPIPeriodicCalState

Format:

```
API8810AFUNC int API8810A SetAPIPeriodicCalState
  int apiNo,
  int nPeriodicCalState
```

Function Description:

This function sends the command to turn on or off the periodic calibration for both channels. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nPeriodicCalState - Turn on or off periodic calibration for both channels
                  Periodic Calibration Types:
                     PERIODIC CAL DISABLED
                     PERIODIC CAL ENABLED
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API_ERROR_WRITE - unable to send command to 8810A
```

References for this function:

None.

API8810A GetAPIPeriodicCalState

Format:

```
API8810AFUNC int API8810A GetAPIPeriodicCalState
  int apiNo,
  int *pnPeriodicCalState
```

Function Description:

This function sends the command to get the periodic calibration setting.

Parameters:

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API ERROR WRITE - unable to send command to 8810A
```

References for this function:

9 API-8810A Buffer Routines

The routines in this section handle sending commands to set and get the configuration for channel buffering on the 8810A.

9.1 API8810A_GetSampleRate

Format:

```
_API8810AFUNC int API8810A_GetSampleRate (
   int apiNo,
   int *pnSampleRate,
   int *pnSampleRateUnit
)
```

Function Description:

This function sends the command to get the sample rate set for angle, angle error, or angle velocity buffering in the 8810A.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) pnSampleRate - pointer to location to return the sample rate pnSampleRateUnit - pointer to location to return the sample rate units Sample Rate Unit Types:

SAMPLE_RATE_MSEC 0

SAMPLE_RATE_SEC 1

SAMPLE RATE MIN 2
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

9.2 API8810A_SetSampleRate

Format:

```
_API8810AFUNC int API8810A_SetSampleRate (
   int apiNo,
   int nSampleRate,
   int nSampleRateUnit
```

Function Description:

This function sends the command to set the sample rate set for angle, angle error, or angle velocity buffering in the 8810A. Note the 8810A

device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nSampleRate - Sample Rate to set for data buffering
nSampleRateUnit - Sample Rate Unit to set for data buffering
Sample Rate Unit Types:
SAMPLE_RATE_MSEC
SAMPLE_RATE_SEC
1
SAMPLE RATE MIN
2
```

Return Value:

References for this function:

None.

9.3 API8810A_GetSampleType

Format:

```
_API8810AFUNC int API8810A_GetSampleType (
   int apiNo,
   char *pszSampleType
)
```

Function Description:

This function sends the command to get the data type being buffering in the 8810A.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
pszSampleType - pointer to location to return the data type being buffered
    Return values:
         "ANG"
         "ANGERR"
         "VEL"
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_WRITE - unable to send command to 8810A

API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

9.4 API8810A_SetSampleType

Format:

```
API8810AFUNC int API8810A SetSampleType
  int apiNo,
  int nSampleType
```

Function Description:

This function sends the command to set the data type to buffer in the 8810A. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nSampleType - Sample Rate to set for data buffering
                  Sample Data Types:
                    BUF ANGLE
                     BUF ANGERR
                                         1
                     BUF VELOCITY
                                         2
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API_ERROR_RANGE_SET - parameter specified is out-of-range
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

9.5 API8810A GetPlotChan

Format:

```
API8810AFUNC int API8810A GetPlotChan
  int apiNo,
  char *pszPlotChan
```

Function Description:

This function sends the command to get the channel being plotted in the 8810A chart.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pszPlotChan - pointer to location to return the channel being plotted
   Return values:
         "BOTH"
         "CH1"
```

"CH2"

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

9.6 API8810A SetPlotChan

Format:

```
API8810AFUNC int API8810A SetPlotChan
  int apiNo,
  int nPlotChan
```

Function Description:

This function sends the command to set the channel to plot in the 8810A. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nPlotChan - Channel to plot
                  Channel Plot Types:
                    PLOT BOTH CHAN
                                         0
                     PLOT CHAN1
                                         1
                     PLOT CHAN2
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR RANGE SET - parameter specified is out-of-range
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

9.7 API8810A_GetAngleErrStep

Format:

```
API8810AFUNC int API8810A GetAngleErrStep
  int apiNo,
```

```
double *pdAngErrStep
)
```

Function Description:

This function sends the command to get the angle step value for angle error comparison for 8810A data buffering.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
pdAngErrStep - pointer to location to return the angle step value for
 angle error comparison for 8810A data buffering.

Return Value:

References for this function:

None.

9.8 API8810A_SetAngleErrStep

Format:

```
_API8810AFUNC int API8810A_SetAngleErrStep (
   int apiNo,
   double dAngErrStep)
```

Function Description:

This function sends the command to set the angle step value for angle error comparison for 8810A data buffering. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
dAngErrStep - Angle step value for angle error comparison for data
  buffering
```

Return Value:

References for this function:

9.9 API8810A GetLowerRange

Format:

```
API8810AFUNC int API8810A GetLowerRange
  int apiNo,
  double *pdLowerRange
```

Function Description:

This function sends the command to get the expected lower range value for 8810A charting.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX API) pdLowerRange - pointer to location to return expected lower range value for 8810A charting.

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

9.10 API8810A SetLowerRange

Format:

```
API8810AFUNC int API8810A SetLowerRange
  int apiNo,
  double dLowerRange
```

Function Description:

This function sends the command to set the expected lower range value for 8810A charting. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
dLowerRange - Expected lower range value for 8810A charting
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
```

API ERROR WRITE - unable to send command to 8810A

References for this function:

None.

9.11 API8810A_GetUpperRange

Format:

```
_API8810AFUNC int API8810A_GetUpperRange (
   int apiNo,
   double *pdUpperRange
)
```

Function Description:

This function sends the command to get the expected upper range value for 8810A charting.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
pdUpperRange - pointer to location to return expected upper range value
   for 8810A charting.
```

Return Value:

References for this function:

None.

9.12 API8810A_SetUpperRange

Format:

```
_API8810AFUNC int API8810A_SetUpperRange (
   int apiNo,
   double dUpperRange )
```

Function Description:

This function sends the command to set the expected upper range value for 8810A charting. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) dUpperRange - Expected upper range value for 8810A charting
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

9.13 API8810A_GetRecordingState

Format:

```
API8810AFUNC int API8810A GetRecordingState
  int apiNo,
  char *pszRecState
```

Function Description:

This function sends the command to get the recording state for 8810A data buffering.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
pszRecState - pointer to location to return the recording state for 8810A
   data buffering
   Return values:
         "NOT RECORDING"
         "RECORDING"
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

None.

9.14 API8810A SetRecordingState

Format:

```
API8810AFUNC int API8810A SetRecordingState
  int apiNo,
  int nRecState
```

Function Description:

This function sends the command to start recording, stop recording or clear the data buffer. Note the 8810A device will not accept the command if its remote communication configuration does not match the communication connection mode.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
nRecState - Buffer Recording command state
Buffer Recording Command Types:
BUFFER_REC_STOP 0
BUFFER_REC_START 1
BUFFER REC_CLEAR 2
```

Return Value:

```
API_SUCCESS - function is successful

API_ERROR_APINO - invalid apiNo parameter

API_ERROR_FUNC_NOT_SUPPORTED - function supported only with

API8810A_NATIVE

API_ERROR_RANGE_SET - parameter specified is out-of-range

API_ERROR_WRITE - unable to send command to 8810A
```

References for this function:

None.

9.15 API8810A_GetBufferCnt

Format:

```
_API8810AFUNC int API8810A_GetBufferCnt (
   int apiNo,
   int *pnBufCnt
)
```

Function Description:

This function sends the command to get the number of data elements in 8810A data buffer.

Parameters:

apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) pnBufCnt - pointer to location to return the number of data elements in data buffer.

Return Value:

References for this function:

9.16 API8810A_GetBufferData

Format:

```
API8810AFUNC int API8810A GetBufferData
   int apiNo,
   int nChannel,
   int nStartRec,
  int nEndRec,
   char *pszBufData
)
```

Function Description:

This function sends the command to get data elements in 8810A data buffer. The number of data elements is the same for Channel 1 and Channel 2. Note data buffer retrieval is available only via USB or Ethernet. Via USB, the maximum number of records returned for each call is 5 data elements. Via Ethernet, the maximum number of records returned for each call is 150 data elements.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
nChannel - Channel to retrieve data
nStartRec - Record number (1 for the first record) to first element to
   retrieve
nEndRec - Record number of last element to retrieve
pszBufData - pointer to location to return data elements in data buffer
   that has been retrieved.
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
API ERROR FUNC NOT SUPPORTED - function supported only with
    API8810A NATIVE
API ERROR WRITE - unable to send command to 8810A
API ERROR DATA - data returned from 8810A is not valid for command sent
```

References for this function:

Prior to calling this function, call API8810A GetBufferCnt() to determine the number of elements in the data buffer. The number of elements is the same for Channel 1 and Channel 2.

Remarks:

Data retrieval of buffered data from the 8810A is available only via the USB (5 data elements maximum with each call) or Ethernet (150 data elements maximum with each call) interface.

10 API-8810A Miscellaneous Routines

The routines in this section handle setting or retrieving information from the API8810ADII and sending freeform commands and queries to the 8810A device.

10.1 API8810A_MaxRetry

Format:

```
API8810AFUNC int API8810A MaxRetry
  int nMaxRetry
```

Function Description:

This function sets the maximum retries to send a command or read a response that will be made when communicating via IEEE. The default value is 0.

Parameters:

```
nMaxRetry - maximum retries for IEEE communication
```

Return Value:

```
API SUCCESS - function is successful
```

References for this function:

None.

10.2 API8810A_LastCmdSent

Format:

```
API8810AFUNC int API8810A_LastCmdSent
  int apiNo,
  char szLastCommand[]
```

Function Description:

This function returns the last command sent via IEEE, USB or Ethernet to the 8810A device.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX API)
szLastCommand - last command sent to 8810A
```

Return Value:

```
API SUCCESS - function is successful
API ERROR APINO - invalid apiNo parameter
```

References for this function:

10.3 API8810A_WriteCommand

Format:

```
_API8810AFUNC int API8810A_WriteCommand (
   int apiNo,
   char szCommand[]
)
```

Function Description:

This function sends the command to the 8810A device.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API) szCommand - command to send to 8810A
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API ERROR WRITE - unable to send command to 8810A
```

References for this function:

None.

10.4 API8810A_QueryCommand

Format:

```
_API8810AFUNC int API8810A_QueryCommand (
   int apiNo,
   char szCommand[],
   char *pszResponse
)
```

Function Description:

This function sends the command to the 8810A device and waits for the 8810A to respond.

Parameters:

```
apiNo - Logical API number assigned to connection with 8810A (1-MAX_API)
szCommand - command to send to 8810A
pszResponse - pointer to location to return the 8810A response to the
command sent.
```

Return Value:

```
API_SUCCESS - function is successful
API_ERROR_APINO - invalid apiNo parameter
API_ERROR_WRITE - unable to send command to 8810A
API_ERROR_DATA - data returned from 8810A is not valid for command sent
```

References for this function:

11 Appendix A – API8810ADII Constant Values

```
/* Maximum number of APIs Driver can communicate with */
#define MAX API 12
/* API Language Types */
#define API8810A NATIVE
#define IEEE API8810 NATIVE
#define IEEE API8810 SR103
#define IEEE API8810 HSR202
#define IEEE API8810 HSR203
#define IEEE API8810 MATECIIL
#define IEEE API8810 FX2
/* API Communication Type */
#define NO CONNECTION
#define IEEE CONNECTION
#define USB CONNECTION
#define ETHERNET CONNECTION
/* Mode Type */
#define RESOLVER
                                 Λ
#define SYNCHRO
/* Reference Source Type */
#define INTERNAL
                                 0
#define EXTERNAL
/* Internal Reference Output State Type */
#define INT REF OUT NOT AVAILABLE
#define INT REF OUT AVAILABLE
/* Angle Display Format Type */
#define ANGLE FMT 360
                                    0
#define ANGLE FMT 180
                                    1
#define ANGLE FMT MIN
/* Angle Limit Format Type */
#define ANGLE LIMIT ABS ANG
#define ANGLE LIMIT ANG ERR
/* DA Format Type */
#define DA ANGLE OUTPUT
#define DA VELOCITY OUTPUT
/* Channel 1 Input Type */
#define CH1_INPUT_FRONT_CONNECTOR
#define CH1 INPUT BACK CONNECTOR
/* Touchscreen Enable State Type */
#define TOUCHSCREEN DISABLED
#define TOUCHSCREEN ENABLED
/* Angle Difference Display State Type */
#define ANG DIFF DISABLED
```

#define ANG_DIFF_ENABLED	1
<pre>/* Periodic Calibration State Type #define PERIODIC_CAL_DISABLED #define PERIODIC_CAL_ENABLED</pre>	*/
<pre>/* Buffer Data Type */ #define BUF_ANGLE #define BUF_ANGERR #define BUF_VELOCITY</pre>	0 1 2
<pre>/* Channel Plot Type */ #define PLOT_BOTH_CHAN #define PLOT_CHAN1 #define PLOT_CHAN2</pre>	0 1 2
<pre>/* Sample Rate Unit Type */ #define SAMPLE_RATE_MSEC #define SAMPLE_RATE_SEC #define SAMPLE_RATE_MIN</pre>	0 1 2
<pre>/* Buffer Recording Command Type */ #define BUFFER_REC_STOP #define BUFFER_REC_START #define BUFFER_REC_CLEAR</pre>	0 1 2
/* Display Command Type */ #define CHAN1_DISPLAY #define CHAN2_DISPLAY #define CHAN1_ANALOG_DISPLAY #define CHAN2_ANALOG_DISPLAY #define DUAL_DISPLAY #define REFERENCE_DISPLAY #define CHARTING_DISPLAY #define UNKNOWN_DISPLAY	0 1 2 3 4 5 6

0

12 Appendix B- Error Codes

Error Mnemonic	Value	Meaning
API_SUCCESS	0	Function is successful
API_ERROR_OPEN_API_SESSION	1	IEEE connection or configuration
		error
API_ERROR_APINO	2	Invalid apiNo parameter
API_ERROR_ADDRS	3	Invalid IEEE Address parameter
API_ERROR_LANG	4	Invalid 8810A Language parameter
API_ERROR_DATA	5	Data returned from 8810A is not valid
		for command sent
API_ERROR_RANGE_SET	6	Parameter specified is out-of-range
API_ERROR_RANGE_GET	7	Value retrieved is out-of-range
API_ERROR_WRITE	8	Unable to send command to 8810A
API_ERROR_USB_CONNECTION	9	USB connection error
API_ERROR_ETHER_CONNECTION	10	Ethernet connection error
API_ERROR_FUNC_NOT_SUPPORTED	11	Function not support in selected
		language for 8810A communication

Revision History

Revision ID	Revision Date	Description	Author
2.0.0.2	Dec 21,2007	Initial Release	gc
2.0.0.3	May 30, 2008	Added API8810A_SetAPIPeriodicCalState and API8810A_GetAPIPeriodicCalState APIs	gc
2.0.0.4	July 31, 2008	Modified the API Soft Panel Screen (p42) to include the additional button that allows the user to read and log the channels' angle data directly to the specified file	gc
2.0.0.15	Mar 30, 2009	Added analog display mode, ability to adjust resolution of angle display, output angles in radians, mil-radians, angle offset option and recall of channel display (ch 1, ch 2 or dual) after power off.	gc
2.0.0.18	Oct 23, 2009	Added API8810A_GetIntRefOvercurrentState and API8810A_ResetIntRefOvercurrentState	gc
2.0.0.19	Mar 17, 2010	For SR103, HSR202, and HSR203, the return angle does not begin with the '<' character, only the 8810A NATIVE has the '<' character.	gc
2.0.0.20	Apr 08, 2010	Added 8810FX2 mode to support automatic setup for the 8810A to the 8810-FX2 configuration	gc
2.0.0.21	Jul 01, 2010	Fixed problem with the IEEE address and Ethernet addresses getting set to factory default values for the *RST? and APICMD RSTFRAM commands.	gc
3.0.0.1	Oct 03, 2012	No changes to API. Updated document revision to correspond to SSK release providing Cypress USB Driver for Windows 7.	gc
3.0.0.2	Nov 16, 2012	No changes to API. Updated document revision to correspond to SSK release 3.0.0.2 which changed the Windows XP and Windows 7 folder names for the Cypress USB Driver.	gc